

SMOS Data Viewer

SDV

Software User's Manual

Code : SDV-DME-TEC-SUM01-E-R
Issue : 2.14
Date : 16/06/2023

	Name	Function	Signature
Prepared by	Daniel Barros	Project Manager	
Reviewed by	Ivo Rodrigues	Project Engineer	
Approved by	Daniel Barros	Project Manager	
Signatures and approvals on original			

DEIMOS Engenharia S.A.
Av. D. João II, Lote 1.17.01, Edifício Torre Zen, 10º
1998-023 Lisboa, PORTUGAL
Tel.: +351 21 893 3010 / Fax: +351 21 896 9099
E-mail: deimos@deimos.com.pt

This page intentionally left blank

Document Information

Contract Data	
Contract Number:	
Contract Issuer:	

Internal Distribution		
Name	Unit	Copies
Internal Confidentiality Level (DME-COV-POL05)		
Unclassified ☒	Restricted ☐	Confidential ☐

External Distribution		
Name	Organisation	Copies

Archiving	
Word Processor:	MS Word 2000
File Name:	SDV-DME-TEC-SUM01-214-E-R_trackchanges

Document Status Log

Issue	Date	Change description
Draft 1	15/06/2006	First draft of the document
Draft 2	14/09/2006	Second draft of the document for FAT-V1
1.4	27/11/2006	Revision 4 of Issue 1: Revision related to SMOS Data Viewer 1.2. Some minor corrections (presentation, spelling and grammar) Section 6 and 7: L1A and L1B features only apply to L1A and L1B data New paragraph in Appendix A (How to edit BinX files) New Appendix B (Prerequisite on the system set-up for printing from SMOSView GUI) New Appendix C (Phase calculations in SMOS Data Viewer plots) New Appendix D about the transformations performed to switch from L1B Fourier components of BT to L1B reconstructed BT
1.5	12/03/2007	Revision 5 of Issue 1: User Manual has been largely revised in each section. The current revision is related to SMOS Data Viewer version beta 1.3, including specific L1C and L2 visualization features. It also takes into account comments from ESA (from February 2007).
2.0	26/04/2007	Issue 2.0: User Manual update for the official SMOS Data Viewer version 1.3.0. Add L2 flag projection section Change explanation for incidence angle selection Add comment concerning the opening of files (.HDR or .DBL) Add search function explanation Add UDP – SM – OS acronyms

2.1	14/06/2007	Revision 1 of Issue 2 : Modifications to take into account comments from FAT-V2 meeting.
2.3	20/11/2007	Add Polarization filter for specific visualization plug-in
2.4	12/12/2008	Update the document in section 5 in order to clarify the SPR SDV-PR-0041. The installation process was further detailed in section 3.2 Updated the L2 Specific Visualization product table
2.5	06/03/2009	Update the document to reflect the new L1C plot functionality in section 8.1. Clarify the IDL export limitations in section 3.5. Updated the auxiliary files that are possible to visualize Added an appendix with the new “Browse” structure of the Level 0 products. This includes the correlations table. Removed “Array Movie Viewer” section Added new section explaining how to replace the product format plugin (section 3.3)
2.6	05/06/2009	Update the document to reflect updates on the color scale and visualization of AUX_SSS and AUX_DISTAN files. Limitations of the Chart Plugin Introduce the new functionality of DUMMY data display for L2 product files
2.7	18/09/2009	Update the document to reflect new implementations on the SMOS Data Viewer release 1.5.4. New specific visualization available fo AUX_FARA products Color scale can be adjusted for L1A and L1B specific visualization panels. The L1B Reconstruction is now performed using the Blackman Apodisation window.
2.8	14/12/2009	Update the document to reflect corrections and enchancements available on SMOS Data Viewer release 1.5.4. • Clarificarification of the specific visualization of CRSx1A • Added section explaining the transformation from square to star domain. • Introduced the support of browsing intermediate products (CORN1A and UCN1A)

2.9	14/05/2010	Update the document to include information about the new specific visualization available for AUX_GAL products in the SDV release 1.6.0. Added information about the new information available in L1A and L1B specific visualization panel.
2.10	17/10/2013	Update the document to include information about the new specific visualization available for AUX_OTT products in the SDV release 1.6.5.
2.11	26/02/2015	Update the document to include information about the new specific visualizations available for AUX_DTBCUR and AUX_DTBXY products as part of the SDV release 1.7.0. New section (3.1) with the Know Issues of the application Corrected typos along the document.
2.12	15/07/2016	Updated Mac OS X installation instructions
2.13	04/01/2019	Updated Windows 8/10 64 bits installation instructions
2.14	16/06/2023	Updated the Windows 10 clarifications in sections 3.1 and 3.3 Updated the AUX_SSS specific visualization description with sub section 9.2.3.1 Updated the AUX_DTBXY specific visualization description with the inclusion of sub sections 9.2.8.4 and 9.2.8.5

Table of Contents

1. INTRODUCTION	16
1.1. Purpose and Scope	16
1.2. The SMOSView mission	16
1.3. Structure of the Document	16
1.4. Abbreviations and Acronyms	17
2. The SMOSView application	19
2.1. Limitations of SMOSView	19
2.2. SMOSView data format	19
2.3. User feedback and bug report	19
3. Getting started with SMOSView	21
3.1. Known Issues	21
3.2. Your system setup	21
3.3. How do I install SMOSView?	21
3.4. Update of New Product Schemas	22
3.5. How do I start SMOSView?	22
3.6. The SMOSView User Interface	23
3.7. SMOSView buffers	25
3.8. The first steps	26
3.9. SMOSView menu tour	26
3.10. SMOSView toolbar	30
3.11. SMOS View Known Problems and Limitations	30
4. Viewing DATA content	31
4.1. File Chooser buffer	31
4.2. Format Manager Buffer	32
4.3. Browser buffer	34
4.3.1. Search function	36
4.3.2. Data browsing in Normal mode	36
4.3.3. Interpreted data	37
4.3.4. Ignored data	38
4.3.5. Other data visualization modes	38
4.4. Export a product subset to an ASCII file	43
4.4.1. Export data using the Browser buffer	43

4.4.2. Export data using the New Subset selection	44
5. Plotting Data	48
5.1. 2D plots	48
5.1.1. Plotting a data field against an auto-generated index	49
5.1.2. Plotting two data fields against each other	52
5.1.3. Importing external data	54
5.1.4. Multi plot visualization	55
5.1.5. Deleting a plot or data selection	56
5.1.6. Saving a plot Template	56
5.2. Plot settings	56
6. L1A Specific visualization features	60
6.1. L1A visibility matrix	60
6.2. What the plot shows	61
6.2.1. Features available	62
6.2.1.1. Zoom in / Zoom out:	62
6.2.1.2. Hide parameters to magnify visualized data:	62
6.2.1.3. Plot Type	62
6.2.1.4. Snapshot and title settings	63
6.2.1.5. Value details	64
6.2.1.6. Export	64
6.2.1.7. Colour Table	65
6.2.1.8. Stepping through the product	68
6.3. L1A Star Domain	69
7. L1B Specific visualization features	70
7.1. L1B Fourier Components of Brightness Temperature	70
7.2. L1B Reconstructed Brightness Temperature	72
8. L1C Specific visualization features	74
8.1. L1C Dual polarization visualization	74
8.1.1. Plot type	75
8.1.2. Pixel Attributes Projection	76
8.1.2.1. Attributes	76
8.1.2.2. Geo Tools	77
8.1.2.3. Projections	78
8.1.2.4. Colour Tables and Range	78
8.1.2.5. Export	79

8.1.2.6. Zoom in / out / around	80
8.1.2.7. Snapshot ID selector	80
8.1.2.8. Polarization	81
8.1.2.9. Incidence angle selector	81
8.1.3. Measurement Counter Projection	81
8.2. L1C Full polarization visualization	82
8.2.1. Polarization	83
8.2.1.1. Brightness Temperatures Specific Plot	83
8.3. L1C browse products visualization	84
9. L2 Specific visualization features	86
9.1. Controls from left pane	87
9.1.1. Field selection	89
9.1.2. Flags selection	89
9.1.3. Geo Tools	91
9.1.4. Projections	91
9.1.5. Field color Scale	91
9.1.6. Example	92
9.2. Error mode	93
9.2.1. Error color scale	93
9.2.2. Error mode example	93
9.2.3. Visualization Approach on AUX_SSS and AUX_DISTAN	94
9.2.3.1. Visualization Approach for the AUX_SSS for schema version 400	95
9.2.4. Visualization of AUX_FARA Products	96
9.2.5. Visualization of AUX_GAL_OS and AUX_GAL_SM	97
9.2.6. Visualization of AUX_OTTxD/F	99
9.2.7. Visualization of AUX_DTBCUR	100
9.2.8. Visualization of AUX_DTBXY	101
9.2.8.1. Plot Panel	102
9.2.8.2. World Map Panel	102
9.2.8.3. Charts Panel	102
9.2.8.4. World map TB bias Panel	103
9.2.8.5. World map GeoPhy Panel	104
Appendix A Prerequisite for Printing	107
Appendix B Phase Calculations in SMOS Data Viewer plots	108

Appendix C	transformations performed to switch from L1B Fourier components of BT to L1B reconstructed BT	110
Appendix D:	Star Domain Visualization	112
Appendix E:	Browse Structure of Level 0 Product Arrays	114

List of Tables

Table 1: List of Terms Used in this Document.....	17
Table 2: List of acronyms used in this document.....	18
Table 3: L1A products to which L1A Specific Visualization Features apply	60
Table 4: L1B products to which L1B Specific Visualization Features apply	70
Table 5: L1C products to which L1C Specific Visualization Features apply	74
Table 6: L2 products to which L2 Specific Visualization Features apply.....	86
Table 7: L2 products to which L2 Specific Visualization Features apply.....	86
Table 8: L2 Ocean Salinity fields that can be projected on the geographical map.....	88
Table 9: L2 Soil Moisture fields that can be projected on the geographical map	88

List of Pictures

Figure 1: SMOSView start window (From top to bottom: Menu bar, Tool Bar, Buffer)	23
Figure 2: Buffer selection box	24
Figure 3: How to split window	24
Figure 4: Multiple (x 4) windows opening	25
Figure 5: File menu	26
Figure 6: View Menu.....	27
Figure 7: System Menu	27
Figure 8: Window Menu	27
Figure 9: Help Menu	28
Figure 10: Right-clicking example	29
Figure 11: SMOSView Icons	30
Figure 12: New file chooser icon	31
Figure 13: File Chooser buffer	31
Figure 14: File chooser icons	32
Figure 15: Folder icon	32
Figure 16: Compatible file icon.....	32
Figure 17: Format manager icon	33
Figure 18: Format manager buffer.....	33
Figure 19: HTML format description example	34
Figure 20: HTML format description navigation icones.....	34
Figure 21: New Browser icon.....	34
Figure 22: Browser buffer example.....	35
Figure 23: Data browsing icons.....	36
Figure 24: Interpreted data representation.....	38
Figure 25: Ignored data flag	38
Figure 26: Flat Mode	39
Figure 27: Hex Mode.....	40
Figure 28: Semantic mode display	41
Figure 29: Tabular Mode.....	42
Figure 30: Transposed table from the tabular mode	42
Figure 31: "Export to ASCII" dialog box	43
Figure 32: ASCII export example	44

Figure 33: Subset selection Window.....	45
Figure 34: Subset selection icons.....	45
Figure 35: New subset dialog box.....	45
Figure 36: Selected data for export example.....	46
Figure 37: Selection of data with scroll bars.....	46
Figure 38: Plot default window.....	48
Figure 39: Plotter buffer icons.....	48
Figure 40: Plot Templates box.....	49
Figure 41: Data Panel.....	49
Figure 42: Product Tree.....	50
Figure 43: Plot screen - Chart Panel.....	50
Figure 44: Array Panel.....	52
Figure 45: Data value against data container index.....	52
Figure 46: XY series Plot template.....	53
Figure 47: XY series example.....	53
Figure 48: XY series with external data.....	54
Figure 49: Import file menu.....	54
Figure 50: Import file example.....	54
Figure 51: Multi Plot example.....	55
Figure 52: All plots icon.....	56
Figure 53: Remove Node icon.....	56
Figure 54: Save Template Icon.....	56
Figure 55: Title renaming example.....	56
Figure 56: color setting menu.....	57
Figure 57: Plotter properties color setting.....	57
Figure 58: Plotter HSB color setting.....	58
Figure 59: Plotter RGB color setting.....	58
Figure 60: L1A visibility matrix example.....	61
Figure 61: Plot Type drop down menu.....	62
Figure 62: Snapshot setting details.....	63
Figure 63: Data field drop down menu example.....	63
Figure 64: Value Details display.....	64
Figure 65: Export Box.....	64
Figure 66: Export formats.....	65
Figure 67: JPG export result.....	65

Figure 68: Color Tables menu	66
Figure 69: Color table example	66
Figure 70: L1A matrix representation using a color table	66
Figure 71: “Display color scale in plot” selected	67
Figure 72: Min and max color scale range selection	68
Figure 73: Snapshot slider	68
Figure 74: Start Domain visualization example	69
Figure 75: L1B Fourier Components of BT example.....	71
Figure 76: L1B Plot type menu	71
Figure 77: L1B Spatial Representation example	72
Figure 78: L1C Specific Visualization Feature Window	75
Figure 79: L1C Plot Type Menu.....	75
Figure 80: L1C Attributes Drop Down Menu	76
Figure 81: Example of L1C BT value field displayed. All pixels displayed refer to the same snapshot (100619).	77
Figure 82: L1C Geo Tools Box Details.....	77
Figure 83: Projections Drop Down Menu	78
Figure 84: North Orthographic projection example	78
Figure 85: Colour Tables Menu.....	79
Figure 86: Export Box	79
Figure 87: Export formats drop down menu	80
Figure 88: L1C Zoom in / out / around Tool	80
Figure 89: L1C Snapshot ID selector box	81
Figure 90: L1C Incidence Angle Selector	81
Figure 91: Measurement Counter Projection L1C example	82
Figure 92: BT vs Incidence Angle Selection Menu.....	83
Figure 93: BT vs Incidence Angle Chart.....	84
Figure 94: L1C browse product visualization example (North orthographic projection)	85
Figure 95: L2 specific visualization feature window	87
Figure 96: Field selection box (OS product on the left; SM product on the right).....	89
Figure 97: Flags selection box.....	89
Figure 98: Flags color transparency menu	90
Figure 99: Flags transparency selection menu	91
Figure 100: L2 field color scale.....	92
Figure 101: L2 OS product visualization example	92

Figure 102: Click on the “Error Mode” icon to start the error mode	93
Figure 103: Error color scale	93
Figure 104: Error mode display above SSS field	94
Figure 105: AUX_SSS Zone PanelDummy Data Filtering.....	94
Figure 106: Display DUMMY Values Option	95
Figure 107: AUX_SSS product visualization for a product schema version 400	96
Figure 108: AUX_FARA Specific Visualization	97
Figure 109: AUX_GAL_OS Specific Visualization	98
Figure 110: AUX_GAL_SM Specific Visualization.....	98
Figure 111: AUX_OTT Dual Pol Specific Visualization.....	99
Figure 112: AUX_DTBCUR Specific Visualization	101
Figure 113: AUX_DTBXY World Map.....	102
Figure 114: AUX_DTBXY Charts Panel.....	103
Figure 115: AUX_DTBXY World map TB bias Panel.....	104
Figure 116: AUX_DTBXY World map GeoPhy Panel	105
Figure 117: Star Domain Representation	112

1. INTRODUCTION

1.1. Purpose and Scope

This document provides a detailed guide to using the SMOSView tool for viewing data from the Earth observation data products contained in binary files. It explains how this data can be extracted, decoded and displayed using various visual representations, including images where appropriate, and exported in a variety of formats.

1.2. The SMOSView mission

SMOS is an Earth Explorer mission dedicated to analyzing the soil moisture and ocean salinity. These parameters are two key variables used within models developed to study the meteorology and hydrology of the Earth. The European Space Agency launched a program aimed at deriving these parameters from Earth satellite observation data, resulting in the SMOS mission.

The SMOS satellite will carry a specific payload named MIRAS (Microwave Imaging Radiometer with Aperture Synthesis), a two-dimensional L-band interferometer radiometer. This instrument will measure the brightness temperature field from which soil moisture and ocean salinity are derived.

INDRA is responsible for implementing the Data Processing Ground Segment (DPGS). This processing facility will ingest raw data down-linked from the SMOS satellite and produce data containing the ocean salinity and soil moisture parameters.

Developing a data processing ground segment is a complex task and requires a data visualization tool. This tool is used to visualize the content of binary data files generated by the ground segment and verify their content. The SMOS Data Viewer is called SMOSView in the following part of this document.

SMOSView is a tool capable of opening and decoding SMOS data. It then displays the contents as tables, graphs as appropriate.

1.3. Structure of the Document

After this introduction, the document is divided into a number of major sections, which are briefly described below:

- ☐ **Chapter 2** presents the SMOSView application and its functionalities.
- ☐ **Chapter 3** details the first steps to use SMOSView; installing the software, system set-up and the User Interface.
- ☐ **Chapter 4** explains how to view product content and format description
- ☐ **Chapter 5** describes plotting capabilities of SMOSView
- ☐ **Chapter 6** details visualization features of L1A data
- ☐ **Chapter 7** details visualization specific features of L1B data
- ☐ **Chapter 8** details visualization features of L1C data
- ☐ **Chapter 9** details visualization features of L2 data
- ☐ **Appendix A** is about the BinX to Xin converter
- ☐ **Appendix B** gives the Prerequisite on the system set-up for printing from SMOSView GUI

- ❑ **Appendix C** details Phase calculations in SMOS Data Viewer plots
- ❑ **Appendix D** may be useful to scientific users who want to understand how SMOSView performed the transformations to switch from L1B Fourier components of BT to L1B reconstructed BT

1.4. Abbreviations and Acronyms

The following terms have been used in this report with the meanings shown.

Data Set	A collection of data set records in an SMOS product.
Data Set Record	A collection of data fields of certain sizes and data types.
Dialog	A window that displays information or presents options to the user.
Focus	The destination of keyboard input.
Java Runtime Environment	The software required to run a Java application
Product	An SMOS data file
View	A manner of visualizing data. E.g. a Graph View or an Image View.

Table 1: List of Terms Used in this Document

The following acronyms have been used in this document:

ASCII	American Standard Code for Information Interchange
ADS	Annotation Data Set (time stamped processing data)
BT	Brightness Temperature
COTS	Commercial Off The Shelf Software
DSD	Data Set Descriptor
ESA	European Space Agency
GIF	Graphics Interchange Format
GUI	Graphical User Interface
HDF	Hierarchical Data Format
HMI	Human Machine Interface
HTML	Hyper-Text Mark-up Language (web page format)
ID	IDentifier (of snapshot)
IDL	Interactive Data Language

IEEE	Institute of Electronic and Electrical Engineers
JPEG	Joint Photographic Expert Group (image format)
JVM	Java Virtual Machine (also Java VM)
data block	Measurement Data Record
MPH	Main Product Header
OS	Ocean Salinity
PDS	SMOS Payload Data Segment (systems processing and archiving data)
PPM	An image format common on Unix
RGB	Red Green Blue
SDV	SMOS Data Viewer also named as “SMOSView”
SM	Soil Moisture
SMOS	Soil Moisture and Ocean Salinity
SPH	Specific Product Header
TIFF	Tagged Image File Format
UDP	User Data Product
VM	(Java) Virtual Machine (used to run java software. Also JVM)

Table 2: List of acronyms used in this document

2. THE SMOSVIEW APPLICATION

The SMOSView software enables a user to decode and display data from SMOS products, display the contents as images or graphs and export the data to several alternative formats.

SMOSView is a tool providing a *quick and easy look* at SMOS data products. Ease of use is emphasized through its simple graphical user interface for data exploration and visualization. This version is intended in particular for the following purposes:

- ☐ Browse through data files and display their content (see section 4),
- ☐ Provide plotting capabilities (see section 5)

2.1. Limitations of SMOSView

SMOSView is not intended for a detailed analysis, visualization, and processing of Earth observation data. There are other commercial and proprietary tools providing these facilities and with many specialized options. However, SMOSView allows selected data to be exported to IDL to support more complex analysis.

Widely used commercial packages include:

- ☐ IDL & ENVI <http://www.itvis.com/>
- ☐ Matlab <http://www.mathworks.com>
- ☐ Mathematica <http://www.wolfram.com/>
- ☐ Noesys <http://www.itvis.com/>
- ☐ PV-WAVE <http://www.vni.com>

2.2. SMOSView data format

SMOSView can handle multiple versions of any Earth observation data products, as long as the product formats are described in the SMOSView format database.

SMOSView handles all these products thanks to the XIN language, an XML meta-data language used to describe the content and structure of any binary data file. The use of XIN language within SMOSView is fully described in the SMOSView Software Specification document.

2.3. User feedback and bug report

User feedback is essential for improving SMOSView and comments and bug reports can be sent directly to the ESA Earth Observation Missions Helpdesk:

<mailto:eohelp@esa.int?subject=SMOSView%20Bug%20Report>

When making a bug report, please include the following information:

From the “About” SMOSView option in the Help menu:

- ☐ Operating System & Machine Type
- ☐ Java version, vendor name and vendor specific
- ☐ SMOSView and data format version numbers

- ☐ Steps leading to problem
- ☐ Any text sent to the terminal

We would like to thank all those who are kind enough to send bug reports and feedback. Every message helps to make the tool better for everyone in the future.

3. GETTING STARTED WITH SMOSVIEW

This chapter presents the first steps to complete before using SMOSView, i.e., installing SMOSView on various platforms and starting the tool.

3.1. Known Issues

The following list presents the known issues of SMOSView that may affect the user interaction with the application:

- ❑ The tool has been tested and supported for Windows XP, Vista and 7 (32 and 64 bits installations). For Windows 8 it is only possible to install the 32 bits installation package. For Windows 10 and beyond an executable is provided for the tool.
- ❑ The Specific Visualization feature of the OTT data from AUX_DTBXY a AUX_DTBCUR products takes around 30 seconds to load. Please wait while the buttons are disabled on the visualization panel.
- ❑ During any Specific Visualization on the World Map the points projected may disappear on some zoom levels. If that happen please center again the map with a click on the center of the navigation arrows.

3.2. Your system setup

SMOSView is a Java application; it can run on any platform. The main requirement for the usage of the tool is RAM memory.

The minimum amount of memory required to launch SMOSView is equal to 512 megabytes, this will allow to use the browse product feature and perform some basic plots (using the chart) of small products.

To use comfortably SMOS View and take advantage of the specific visualization feature up to Level 1C it is recommended to have at least 1 GB of memory. To use the specific visualization of L2 ADFs and L2 products it is recommended to have 2GB dedicated to SMOS View.

SMOSView is fully supported only on Java 1.5, which is included in the installation package. For more information, please refer to www.java.com.

NOTE: On 64 Bit operating systems installations, the library glibc-32 bits version is required to be installed.

3.3. How do I install SMOSView?

SMOSView provide installation packages for Microsoft Windows, Mac OS X, AIX, Solaris, Linux and HP-UX operating systems.

Unzip the archive, open the file “install.htm” with your web browser and download the installation file for your architecture. The installation instructions presented below are also available in the page.

Windows XP, Vista, 7:

- After downloading, double-click “install.exe”
- You do not need to install any other software. A Java virtual machine is included with this download.

Windows 8/10 32 bits installation

- After downloading, right-click on “install.exe” and select "Properties"
- On the "Compatibility" tab enable the Compatibility mode and select "Windows 7" and press "Ok"
- Double-click “install.exe”

Windows 8/10 64 bits installation

- After downloading, unzip the file to a chosen directory.
- Navigate to most recent SMOSView directory and double-click “smosview” executable

Mac OS X:

- After downloading, double-click “install”.
- Requires Mac OS X 10.4 or later
- Be sure you have Java Virtual machine compliant with version 1.5 installed.
- Make sure that the system allows the installation of software downloaded from everywhere. This can be set in "System Preferences" -> "Security & Privacy".
- The compressed installer should be recognized by Stuffit Expander and should automatically be expanded after downloading. If it is not expanded, you can expand it manually using Stuffit Expander 6.0 or later.

AIX / Linux / HP-UX:

- After downloading open a shell and, “cd” to the directory where you downloaded the installer.
- At the prompt type: “sh ./install.bin”
- A Java virtual machine is included with this download. It will run automatically when you run the shell script.

3.4. Update of New Product Schemas

SMOS View install by default a “jar” file (smos-formats-plugin-SNAPSHOT.jar) containing the latest XIN and XIS SMOS product schemas available on the date of the release, however new schemas releases may happen and this does not mean that a new version of the software shall also be distributed.

SMOS View has the possibility to replace the product schemas jar file with a newer version and the new products can instantly be read. The process is very simple; the user just needs to replace the old “smos-formats-plugin-SNAPSHOT.jar” file with the new one.

The “smos-formats-plugin-SNAPSHOT.jar” is located in the directory where SMOS View was installed.

3.5. How do I start SMOSView?

In order to run SMOSView:

- ❑ On Microsoft Windows: In the 'Start' menu, click on the SMOSView shortcut in the SMOSView group menu.
- ❑ On an X Windows system (UNIX/Linux) or a BSD based system (Mac OS X): Open a terminal and cd in the SMOSView installation directory. Then type `./SMOSView`.

3.6. The SMOSView User Interface

When SMOSView starts, a large window appears containing a *menu bar*, a *tool bar* and an area just below known as a *buffer*, as shown in the Figure 1.




Figure 1: SMOSView start window (From top to bottom: Menu bar, Tool Bar, Buffer)

A window may contain many buffers, and a drop-down list at the top of the buffer area is used to switch between buffers; *the buffer selection box*. To open this selection box as shown in the Figure 2, the user must click on its label. In this example, *the buffer selection box* is labeled: [FILECHOOSER] C:\SMOSView\SMOS TEST PRODUCT\L1A-L1B.

The buffer selection box could also be labeled [BROWSER] followed by the product name if a product is being browsed or [SMOSSVF] followed by the name of the product if the product is being studied with the Specific Visualization Features.

After more than one buffer has been opened, it is possible to come back to a dedicated buffer by clicking the *buffer selection box* located under the main window icons and selecting the buffer of interest.




Figure 2: Buffer selection box

Multiple buffers can be displayed in the window at the same time, by *splitting* the window horizontally and or vertically. It can be done by choosing “Split horizontally” or “Split vertically” in the “Window” menu of the menu bar (see Figure 3 and also Section 3.9, Window Menu Figure 8).




Figure 3: How to split window

Split window sections can be closed by “Unsplit” in the “Window” menu of the menu bar.

The same list of buffers is available in each split window section.

Multiple windows may also be opened (see Figure 4, where 4 window-areas have been opened), and within each window, an independent list of buffers may be opened.




Figure 4: Multiple (x 4) windows opening

A buffer is a SMOSView window containing a set of functionalities/tools associated with a product. Once a product data file is selected with the File Chooser buffer as described in section 4.1 of this document, the user can use the SMOSView functionalities associated with the selected data product by opening a Lat/Long plot, a Plotter or an Image Viewer buffer.

The use of the Format Manager buffer does not require any product to be opened before using it.

3.7. SMOSView buffers

Interaction with data files and the various tools and views provided by the application is through buffers. The current version of SMOSView provides the following buffers:

-  **File Chooser** buffer – presents a view of the file system, and identifies compatible files that can be opened with SMOSView
-  **Export to ASCII** – allows to export selected data to an ASCII file (.txt extension)
-  **Export to IDL** – allows to export selected data to IDL (2 files are created with .pro extension and .dat extension)

NOTE: There is a limitation on the export IDL feature on variable size arrays. IDL export works correctly if only one pixel is exported. When more than one pixel is exported only the first N-

measurements for each pixel are exported. N is the number of measurements of the first pixel selected.

-  *New Browser* buffer – presents a view of the contents of a data file.
-  *New Chart* – allows the user to plot data
-  *SMOS Specific Visualization features* – allows the user to analyze SMOS L1A, L1B, L1C and L2 products
-  *New Format Manager* buffer – presents a description of each of the file formats supported by SMOSView.
-  *New Subset Selection* buffer – allows the user to select a data set inside the product
-  *Help* – opens the user guide in HTML format

3.8. The first steps

After starting SMOSView, the default window appears which contains a single File Chooser buffer. This allows one to navigate the file system and select a file that can be opened in the application.

At this stage, all the available menus are displayed, but many of the menu items are disabled.

To start viewing data, select a compatible file in the File Chooser, and open a buffer to view the contents (via the toolbar or the buffer menu).

It is also possible to view format descriptions for compatible files via the Format Manager.

The File Chooser buffer is described in section 4.1 and the Format Manager buffer is detailed in section 4.2.

3.9. SMOSView menu tour

This section describes the menus available in SMOSView in version 1.5.2.

The **File menu** enables the user to open a File Chooser buffer or quit the program.



Figure 5: File menu

The **View Menu** enables the user to open a Browser buffer or a Plotter or specific visualisation features buffers. The buffers are only available once a product has been selected (see section 4.1). The Browser, Plotter and specific visualisation features will only be available if a compatible data file has been

selected. After selecting a product, if the user tries to use SMOSView functionality not available with the product, SMOSView will display an empty window.




Figure 6: View Menu

The **System menu** enables the user to open the Format Manager buffer, providing a description of the formats contained within SMOSView, as well as a New Logger buffer, giving detailed information on the current SMOSView session as to memory usage, Java version and error reporting.




Figure 7: System Menu

The **Window menu** enables the user to open a new window, close a window, or split/unsplit a window.





Figure 8: Window Menu

Splitting a window is useful for working with more than one product, or visualizing an image and the related data product file at the same time. (i.e. two or more buffers simultaneously)

For example, a Format browser buffer and an Image Viewer buffer may be viewed side by side by clicking on the Split horizontally menu item, and then selecting the Image Viewer buffer in the second split section.


The sixth menu in the menu bar is buffer specific, it means it depends on the content of the current buffer. This 6th menu provides access to options specific to each buffer type:

- ☐ When a file chooser is opened, the 6th menu proposes either to go to the home folder, or to the parent folder, or to refresh the current window:




- ☐ When a browser is opened, the 6th menu proposes various options to visualize the content of the selected product: visualization mode selection (normal mode, flat mode, Hex mode, Semantic mode,


or tabular mode), browsing options (go to the parent element, to the previous or the next brother, to the previous or the next cousin, or printing options:



- When a Plotter buffer is opened, a Plotter menu appears. Depending on the selected field (Plot/Series/Data), the selectable options are different. They could be: Add Plot, Add Series from product, Add XY series, Add data from file, Add data from product, Remove node, save template, export chart, or print chart:



- When the specific visualization feature (SVF) buffer is opened, the 6th menu is not an SVF specific menu but the help menu:



The **Help menu** provides an access to the user guide (based on this document).




Figure 9: Help Menu

After a buffer is opened, right clicking in a buffer will display additional context sensitive menu options, associated with that buffer as well as a shortcut to some the menus in the menu bar. For example, after opening a Format Browser, right clicking in the buffer will display the following menu:




Figure 10: Right-clicking example

3.10. SMOSView toolbar

Below the menu bar, a toolbar is provided as shortcuts for common tasks:

- ☐ File chooser
- ☐ Export to ASCII
- ☐ Export to IDL
- ☐ Format Browser
- ☐ Plotter
- ☐ SMOS Specific visualization features
- ☐ New Subset Selection
- ☐ HTML format description
- ☐ User guide



Figure 11: SMOSView Icons

Toolbar icons are only highlighted when the associated functionality is ready for use. For example, after opening SMOSView, the "Export to ASCII" is greyed, as there is no file open to export data from.

3.11. SMOS View Known Problems and Limitations

Before the user starts to use SMOS View, it shall be clear that the tool have some limitations and some known problems specially on big product files. This section contains some important information related to these issues and will be updated along with the new releases of the tool.

- The chart plugin has memory limitations, when the user tries to plot a variable from a product with a high number of points (more than 2 million) it is very slow and sometimes just freeze. This happens on products such as LAI, AUX_SSS, AUX_DISTAN, and some L2 products.
- In the browser plugin some indications that the data is loading is missing. Sometimes it is still loading data and no information is shown. This usually occurs on big product files.
- The specific visualization panel has refresh problems, sometimes when the user tries to visualize L2 flags they don't appear in the world map, however if the user zooms an area the flags appear.
- When the user tries to use the specific visualization L2 data (especially AUX DGG files) the specific visualization panel is loaded and became completely grey, user must resize the window view the content correctly.

4. VIEWING DATA CONTENT

This chapter details the use of SMOSView for viewing products.

4.1. File Chooser buffer

In order to select a product for analysis in SMOSView, select a File Chooser buffer (one is opened by default at startup), or click on the "New Filechooser" icon.



Figure 12: New file chooser icon




Figure 13: File Chooser buffer

It is possible to navigate through to common directories using the “Home directory”, “Parent directory”, or “Drive selection” toolbar icons.

☐ Home directory icon: 

☐ Parent directory icon: 

☐ Refresh view icon: 

☐ Previously accessed directory: 

☐ Drive selection: 




Figure 14: File chooser icons

The “Refresh view” icon enables the user to update the view of the current folder if a file has been added/deleted from/to the folder since list was first displayed. The location bar provides the location of the selected directory/file. Folders are highlighted with a blue icon.



Figure 15: Folder icon

Double click on a folder to view its contents. Use the Parent directory toolbar icon to go up to the directory level above the current list.

Once the data is located, files compatible with SMOSView are highlighted with the following icon:



Figure 16: Compatible file icon

It is then possible to select the data of interest by simply clicking once on the file of interest. Once the file is selected, it is highlighted in yellow.

To open a compatible data, the user must double click on its name. The data will then be automatically opened in a new Browser buffer, displaying the content of that file (see section 4.3).

After selecting a product, a user can browse through its content using the format browser.

To open a file, the user can either double click on its header name (.HDR) or on its data block name (.DBL).

It is also possible to browse some intermediate products such as CORN1A and UNCN1A in EEF format. In this case SDV automatically generate the corresponding HDR and DBL files allowing the user to browse the content.

4.2. Format Manager Buffer

In order to view format descriptions of compatible data files, click on the "New FormatManager" icon.



Figure 17: Format manager icon




Figure 18: Format manager buffer

The FORMAT MANAGER buffer contains the list of file formats that are recognized by SMOSView and potentially multiple versions of each format.

The version gives the global version of the format, not the header or the datablock version.

The list is obtained by inspecting the formats shipped with SMOSView, therefore the list is always in line with the list of products that can be read using SMOSView.

Double click on any of the formats to visualize the detailed description.




Figure 19: HTML format description example

Format information is available as a hierarchy, through which one navigates by clicking on blue links “Details”, similar to a web page.

Once the “Details” page opened, it is also possible to navigate through the format descriptions using the "Previous page", "Next page", or "Reload page" toolbar icons placed in the top left corner of the window.



Figure 20: HTML format description navigation icons

4.3. Browser buffer

Select a file in the File Chooser (section 4.1) and create a Browser buffer by either double clicking on the product file, or clicking once on the highlighted "New Browser" icon.



Figure 21: New Browser icon




Figure 22: Browser buffer example

The Browser buffer has several display *modes*; Normal mode, Flat mode, Hex mode, Semantic mode and Tabular mode. By default, the Browser buffer opens in Normal mode.

The buffer is divided in two panes: On the left-hand side we find a hierarchical view of the content of the file and on the right-hand side, we find the content of selected parameter or structure, and interpretation of the field values and description.

A tool bar is displayed at the top of the buffer with several toolbar icons to allow switching between the different modes and navigating through the selected file.

- ☐ Normal mode 
- ☐ Flat mode 
- ☐ Hex mode 
- ☐ Semantic mode 
- ☐ Tabular mode 

- ☐ Parent element 
- ☐ Previous element 
- ☐ Next element 
- ☐ Previous cousin 
- ☐ Next cousin 
- ☐ Print browser panel 



Figure 23: Data browsing icons

There are two types of icons within the browser window:

- ☐  Representing a data container.

A data container can contain other data containers or leaf nodes.

- ☐  Representing a leaf node, containing data.

4.3.1. Search function

The user can search for a field name or a value within the product with the search function at the bottom of the browser window.

4.3.2. Data browsing in Normal mode

One single click on a container (blue-folder icon) in the left-hand pane will display the content of the container in the right-hand pane.

Double clicking on a container in the left-hand pane will provide the content of the container in the right-hand AND left-hand panes.

It is also possible to browse through a product with one single click on the tree opening symbols associated with a data container in the left-hand pane:

-  *tree opening symbol*

Clicking on a leaf node in the left-hand pane will provide a view of the parent node in the right-hand pane; the selected leaf node will be highlighted in the right-hand pane.

It is also possible to visualize the content of a container by double clicking on it in the right-hand pane. In this case, the container is highlighted in the left-hand pane.

It is possible to browse through the product using the “Parent element”, “Previous element” and “Next element” icon. Using the “Next” and “Previous” icons enables the user to view the next or previous element within a container. Using the “Parent” icon enables the user to view the higher-level data container.

In the context of SMOSView, two cousins are data containers or leaf node belonging to a repeated structure within a data block. It is also possible to browse through the products clicking the Previous cousin and Next cousin Icons. When a leaf node or data container is selected within a data block, clicking on the next/previous cousin will provide same leaf node or data container view of the next/previous data block.

Example: for a SMOS L1B data product, the user selects and clicks on the Snapshot_ID in a container “binary-data/Data_Block/Temp_Snapshot_dual/ Temp_Snapshot_dual/**item 7**”.

=> Clicking on the Next cousin icon, SMOSView will show the Snapshot_ID of “binary-data/Data_Block/Temp_Snapshot_dual/ Temp_Snapshot_dual/**item 8**”.

When a leaf node is selected, the location bar provides the path to the higher-level container. When a container is selected, the location bar provides the path of the container within the product.

4.3.3. Interpreted data

“Interpreted data” are elements of a data file whose numerical value is translated into human readable form.

For example, considering a SMOS L1B product, in the container:

“binary-data/Data_Block/Temp_Snapshot_dual/ Temp_Snapshot_dual/item 7”, the field “**Flags**” is interpreted. The field can have several integer values, but SMOSView is capable of decoding the meaning of those values. For instance, the value 0 corresponds to H (horizontal polarization).

The same applies to another field in this container: for example Snapshot_Time (day 2610 has been interpreted as 23-Feb-2007).

In the right-hand side window, interpreted data appear within a yellow box:

	Ix	Name	Interpretation	Description
	1	Snapshot_Time	23-Feb-2007 18:25:09 599.960	
	2	Snapshot_ID	101504	
	3	Snapshot_OBET	7349874607129204736	
	4	X_Position	-181043.5	
	5	Y_Position	-1033994.6875	
	6	Z_Position	7051289.0	
	7	X_Velocity	-7504.6806640625	
	8	Y_Velocity	841.3841552734375	
	9	Z_Velocity	-69.25267028808594	
	10	Vector_Source	1	
	11	Q0	0.7562666535377502	
	12	Q1	0.3253655731678009	
	13	Q2	0.5668948292732239	
	14	Q3	0.028779638931155205	
	15	Flags	HH	
	16	Scene_BT_Fourier	2791 items	
	17	Accuracy	296.49533	
	18	Average_System_...	270.33072	
	19	Physical_Temperat...	0.8155929	
	20	LICEF_Status	2 items	
	21	Direct_Sun_Pos	2 items	
	22	Direct_Sun_BT	0.0	
	23	Reflected_Sun_Pos	2 items	
	24	Reflected_Sun_BT	104.83751906030892	

Figure 24: Interpreted data representation

Interpreted data can apply to leaf nodes or containers.

For example, in the SMOS L1B data product, the Snapshot_Time container, consists of 3 fields: Day, Seconds, and Microseconds, but can be interpreted as a human readable time.

It is also possible to read the numerical value associated with an interpreted data when a data container is interpreted. Double-click on the data container, SMOSView will display the numerical value of the interpreted fields. Clicking back on the parent data container changes the field back to the interpreted value.

4.3.4. Ignored data

If SMOSView expects to read an integer, and read an unsigned integer the product, it is flagged in the following way:

	2	item	65535.0 (Ignored)
---	---	------	-------------------

Figure 25: Ignored data flag

4.3.5. Other data visualization modes

Data selected in “Normal” mode can be visualized in other modes using the icons placed on the top left-hand side of the BROWSER.

☐ "Flat mode":

If a container is selected, all data within the container are displayed in the right-hand pane down to the lowest leaf level in a hierarchical order. If a leaf node is selected, the parent container is displayed in flat mode in the right-hand pane.




Figure 26: Flat Mode

❑ "Hex mode":

In Hex mode the whole product file is displayed in hexadecimal format in the right-hand pane. The data selected in the browse tree is also highlighted in yellow in the right-hand pane.




Figure 27: Hex Mode

□ “Semantic mode”:

This mode shows all the semantic data contained within a field of interest. In the case of SMOSView, it should not be useful, except for L3 or L4. The semantic data is limited to images. If a product or a subset of a product contains an image, clicking on the semantic mode icon will display the available images and related channels in the right-hand pane.




Figure 28: Semantic mode display

Using the semantic mode, it is possible to open an Image Viewer buffer by selecting one or more channels from the right-hand pane. The user can select to visualize a single channel of interest with a simple mouse click. To select multiple channels of interest hold the “Ctrl” key pressed and click on the additional channels until they are highlighted.

□ “Tabular mode”:

To use this mode, the user needs to select a sequence of data or an array (which could be a data container).

The tabular mode allows to visualize all the selected values (or the values contained in the array) in a table that may be transposed (see Figure 29).

To transpose the matrix, click on the upper left cell labeled “tt”.

The elements of the transposed table (see Figure 30) can be copied/pasted in another application.

SMOS-view 1.3

[BROWSER] SM_TEST_MIR_SC_D1A_20070223T061024_20070223T062500_001_001_0

/binary-data[1]/Data_Block[1]/Calibrated_Visib_Dual[1]/Calibrated_Visib_Dual[1]/item[1]/Calib_Visib[1]

tt	r	i
item 1	-8.891413487745902	-1.2400731520040735
item 2	2.9275949868302816E-6	-1.17620975029984E-6
item 3	4.370773522970448	-3.2191311650342564
item 4	5.5262066195287725	2.1127470848279075
item 5	-2.5453373817991523	4.578882052638973
item 6	-2.8751521022655906	-3.668260471872994
item 7	0.5635571242170587	1.1389724881151098
item 8	-0.3016964227007277	-1.9588172027406843
item 9	-0.3165580149622741	0.4478656850800639
item 10	-0.11230895144506636	0.09764967857837716
item 11	-0.13375699774730607	0.20260035599529533
item 12	0.3476344197680819	-0.6510738517980369
item 13	-0.512616547679971	-0.009591971862912734
item 14	-0.883271567275264	-0.25691172221167496
item 15	0.008397598845364245	-0.686416178046936
item 16	0.7208609944860824	-0.7898537320952079
item 17	0.48095506620738265	0.12692387447491055
item 18	0.22511606779090712	0.08249408398612951
item 19	-0.05298847327065589	0.1340651233242866
item 20	-0.05254061742565381	-0.04103156479519035
item 21	-0.2519245847631593	-0.0978439533860581
item 22	0.0011873172951424055	-0.17220103969915343
item 23	0.04224982465751189	-0.19921558408924986
item 24	1.7717084259101044	0.6010508841390391
item 25	-0.8608793503069623	0.38532211328902605
item 26	-2.301804632880485E-5	-9.628615875904891E-6
item 27	-1.9255818243480307	4.18567146723326
item 28	-7.529099226920834	1.7676469911303134
item 29	-3.837110212763945	1.8873837523393002
item 30	1.1170313095273021	-0.031137115077189314

Search :

Figure 29: Tabular Mode

SMOS-view 1.3

[BROWSER] SM_TEST_MIR_SC_D1A_20070223T061024_20070223T062500_001_001_0

/binary-data[1]/Data_Block[1]/Calibrated_Visib_Dual[1]/Calibrated_Visib_Dual[1]/item[1]/Calib_Visib[1]

	item 1	item 2	item 3	item 4	item 5	item 6	item 7	item 8	item 9	item 10	item 11
tt	-8.891413487...	2.927594986...	4.370773522...	5.526206619...	-2.545337381...	-2.875152102...	0.563557124...	-0.301696422...	-0.316558014...	-0.112308951...	-0.133756997...
r	-1.240073152...	-1.176209750...	-3.219131165...	2.112747084...	4.578882052...	-3.668260471...	1.138972488...	-1.958817202...	0.447865685...	0.097649678...	0.202600355...
i	-0.686416178...	-0.789853732...	-0.097843953...	-0.172201039...	-0.041031564...	-0.097843953...	-0.172201039...	-0.041031564...	-0.097843953...	-0.172201039...	-0.041031564...

Search :

Figure 30: Transposed table from the tabular mode

4.4. Export a product subset to an ASCII file

The Export to ASCII can be performed in two ways:

4.4.1. Export data using the Browser buffer

In order to export a product subset to an ASCII file, it is first necessary to select the data of interest inside a Browser buffer.

When the Browser is in “Normal mode” or “Flat mode”, use the right-hand pane to select containers and/or leaf nodes of interest that you would like to export.

To select multiple items, hold the “Ctrl” or “Shift” key while selecting containers and nodes. (CTRL + Click for selecting non-consecutive items, Shift for selecting consecutive items).

Upon pressing the "Export to ASCII" icon in the toolbar , an "Export to ASCII" dialog box appears allowing you to perform an ASCII export.





Figure 31: "Export to ASCII" dialog box

You can then choose to perform a Hierarchical export or a Tabular export.

With the Hierarchical export, the user can choose to export:

- the element name
- the element offset
- the element value
- the element unit.



```
r,i
2.967185632662037,-3.135572213087803
r,i
1.6070597123739485,4.288792526093562
r,i
-0.10310220944316402,0.3230501356267048
r,i
-0.4825514584203187,0.1884402773536982
r,i
-0.04592285227172175,0.2015337801705091
r,i
0.3838733505642699,-0.4283243998280542
r,i
-0.5370477589183219,-0.09375588147961446
r,i
0.38732985546880705,0.47486761007437217
r,i
0.7201885064024937,-0.7195504754446704
r,i
-1.1182951807784869,-0.5088450612181198
r,i
0.0031850304947010533,0.44905932432695933
r,i
-0.1072257535754707,-0.27875754808812536
```

Figure 32: ASCII export example

The example in Figure 32 shows the type of output that is produced by the "Export to ASCII" Hierarchical option. Note that the file has a ".txt" extension.

With the Tabular ASCII, the user has the possibility to select the separator type as well as inserting a column header or not. The Tabular ASCII is very useful if the user wants to export its data in Excel for example. In that case, the user should set as a separator a single comma “,” and then save the file in the csv format. The user can then open the saved file using Excel.

It is important to notice that the Tabular ASCII export function needs to be used with properly selected coherent data. If you try to export a two-dimensional array structure over a repeated number of data blocks along with data contained in the product header for example, there is no guarantee that the export will be satisfactory. On the contrary, if the selected data is coherent, i.e. the selected data is of the same hierarchical level, and containing no dummy data, the Tabular export to ASCII is the perfect tool for allowing further processing with other tools.

4.4.2. Export data using the New Subset selection

It is also possible to select the data to export clicking on the “New Subset” icon. Select a file in the File Chooser (section 4.1) and click on the “New Subset” icon. The following Window appears:




Figure 33: Subset selection Window.

On the top left hand side window area, the user can find the following Icons:




Figure 34: Subset selection icons.

The user can then click on the New Subset blue icon : he must enter a name for the new subset to be created and click OK:




Figure 35: New subset dialog box

Then the product structure will appear in the right-hand side window. The user can then select and browse through the product structure and select the data to export simply clicking in the selection box attached to the data to be exported (see Figure 36).




Figure 36: Selected data for export example

The user can then save the created subset, rename it or delete it clicking on the icons presented in Figure 34: Subset selection icons. The saved subset will be available next time the user opens the product.

When a product is made of repeated data structures, you can use scroll bars at the bottom of the selection window to select the subset of data to export, as shown in the example below:




Figure 37: Selection of data with scroll bars

The selected data product contained 2791 Scene_BT_Fourier items. For the scroll bars to be available, the user needs to click on the item array container Scene_BT_Fourier [1..2791] selection box. This

makes the scroll bars appear, the user can then select a subset of items to export by dragging the cursors along the bar by clicking and dragging one of the cursors with the left mouse button pressed.

To complete the export, the user must click on the Export to ASCII Icon in the tool bar and proceed in the same way as described in the previous paragraph.

Once more, the user must select data carefully to perform a valid Export in a Tabular format.

5. PLOTTING DATA

SMOSView allows the user to perform 2D and 3D plots using the 2D plotter buffer and the 3D plotter buffer.

In order to avoid out of memory issues caused by the chart plugin, the maximum number of points that is possible to plot is limited to the first 600.000. If the user tries to plot a variable with a higher number of points a warning message is displayed and the limited plot is produced.

NOTE: It shall be noted that in versions of SDV prior to 1.5.2 the data is loaded in memory and then displayed. Any change on the display preferences will imply a reload of the data into memory.

5.1. 2D plots

In order to use the 2D plot, the user must select first a file using the File Chooser buffer as presented in section 4.1 of this document.

The user can then click on the New Chart Icon ; the following window appears:




Figure 38: Plot default window

The following icons are available on the top left hand side of the plotter window:



Figure 39: Plotter buffer icons

From left to the right, the following Icons provide the following functions:

- Add plot
- Add Series from Product
- Add XY Series
- Add data from File
- Add data from Product
- Remove Node
- Save template
- Export Chart
- Print Chart

5.1.1. Plotting a data field against an auto-generated index

In the “**Plot Templates**” Box (Figure 40), the user must click on the magnifier icon  of “Plot_1”, then “Serie_1”, then “Data_1”.




Figure 40: Plot Templates box

A new panel, the “**Data Panel**” box becomes active (Figure 41), below the Plot Templates box.




Figure 41: Data Panel

The user must browse inside the data to select data field of interest to be plotted with the Product Tree (See panel on the lower left, Figure 42): The user has then to click on the field of interest to plot it.




Figure 42: Product Tree

While browsing the data deep inside the “Product Tree” another panel becomes active, which is the “Chart Panel” (big window in the middle). It corresponds to the panel where the plot is displayed, as seen in Figure 43.

The plotter will then try to display the selected data field. If the selected data field is contained within a repeated structure inside the data product file, the plotter will show the selected data field value against the repeated data structure index.

If the data field is contained inside two subsequent repeated data structures, the user has the option to select the index of one data structure or the other.




Figure 43: Plot screen - Chart Panel

Let's have a look at the following example:

Let's assume that the field Y_TO_PLOT is contained within an array or structure called CONTAINER_LEVEL_A of size N. Let's assume that CONTAINER_LEVEL_A is contained within an array or structure CONTAINER_LEVEL_B of size M and so on.

CONTAINER_LEVEL_C 1

CONTAINER_LEVEL_B 1

CONTAINER_LEVEL_A 1

Y_TO_PLOT 1
Y_TO_PLOT 2
Y_TO_PLOT 3
.....
Y_TO_PLOT N

CONTAINER_LEVEL_A 2

Y_TO_PLOT 1
Y_TO_PLOT 2
Y_TO_PLOT 3
.....
Y_TO_PLOT N

.....

In such a case, the user may want to plot:

- Y_TO_PLOT data can be plotted against indices of the CONTAINER_LEVEL_A 1 array
- Y_TO_PLOT 1 can be plotted against CONTAINER_LEVEL_A 1, CONTAINER_LEVEL_A 2 and so on.
- Y_TO_PLOT 1 of CONTAINER_LEVEL_A 1 can be plotted against CONTAINER_LEVEL_B 1, CONTAINER_LEVEL_B 2 and so on.
- Y_TO_PLOT of CONTAINER_LEVEL_A 1 in CONTAINER_LEVEL_B 1 can be plotted against CONTAINER_LEVEL_C 1, CONTAINER_LEVEL_C 2 and so on.

In all cases, the “Array” menu will offer the possibility to select different (X, Y) data sets at the following level of the data block: CONTAINER_LEVEL_A, CONTAINER_LEVEL_B or CONTAINER_LEVEL.




Figure 44: Array Panel

The user can also select the index range using the sliders under the array index selection box to modify the selected data. To change the slider position, set the mouse cursor over the slider icon, click left with the mouse and maintain the button clicked, drag then left or right the mouse.




Figure 45: Data value against data container index

5.1.2. Plotting two data fields against each other

The user can create an XY plot with data contained inside the product data file:

First, repeat the previous steps to select data to be set on the X axis.

To select data to be set on the Y axis, click on the Serie_1 Icon  , click then on the “add data from product” icon  . A Data_2 icon appears in the Plot Templates box, and the Plot_1 icon changes as well to the “add XY series”. See Figure 46.




Figure 46: XY series Plot template

The user must then browse through the product tree to set data on the Y axis just as he did for the X axis, opening and browsing through the product tree.

Note that X-axis data always corresponds to the first (upper) icon in the Series list and the Y-axis always corresponds to the lower one.




Figure 47: XY series example

5.1.3. Importing external data

With the SMOSView data plotter, it is possible to import numerical data stored in a file on a computer.

If the user clicks on the Plot_1 icon , and then clicks on the add XY series , the following appears:



Figure 48: XY series with external data

The Data_3 icon corresponds to X-axis data that must be imported from an external data file.

In this example, let's click on the Data_3 icon: The following menu appears:



Figure 49: Import file menu

The user can then Click on the “Browse” tab and select a file containing numerical values. Data to be imported must be contained in an ASCII file with one single value per line.

As an example, let's import the following file:




Figure 50: Import file example

The user can then complete the plot by clicking on the Serie_2 icon  and then on the “Add Data From Product Icon”  to select data to be set on the Y-axis as described in the previous section.

Data can also be imported on the Y-axis. When the plotter is in the configuration described in section 5.1.2, instead of clicking on the “Add Series From Product” icon, the user can click on the “Add Data From File”  icon and follow the same steps described here above to import the data file.

5.1.4. Multi plot visualization

The user can visualize several plots in the same chart within the Plot_1.

He must select the first series with the product tree following the steps detailed previously.

He will add another series in the chart by clicking on Plot_1 icon  , and then clicking on the “Add Series From Product” icon  . The user can follow the steps for data selection with the product tree as described in the section here above.

The user can see the resulting plots on the same graph by clicking on the Plot_1 icon  .




Figure 51: Multi Plot example

For the multi-plot to be available and easy to read, the user shall take care about the data selected on the X-axis and make sure that the ranges and X-axis units are coherent. For example, if the user creates a first curve whose X-axis values range from 1 to 10 (Index), and a second plot whose values range from –100000 to +49000 (mm), there will be a visualization issue on the multi-plot display.

As a rule, the multi-plot will use the unit (or index) of the first plot created within the Plot_N template and only show those curves whose unit (or index) is the same as the first plot.

Data on the Y-axis can be of any unit, the corresponding scale will be shown on the right-hand side of the multi-plot.

The user can create any number of multi-plots by clicking on the “All plots” icon and then clicking on the “Add Plot” icon.




Figure 52: All plots icon

5.1.5. Deleting a plot or data selection

The user can easily remove individual plots, by clicking on the plot icon (typically, Serie_N icon) and then clicking on the “Remove Node” icon.



Figure 53: Remove Node icon

He can also remove entirely a plot (typically, Plot_N icon), and click on the “Remove Node” icon.

5.1.6. Saving a plot Template

The user may want to be able to plot the same data fields using different product files of the same type. SMOSView allows the user to save a plot template and reuse it with other data products of the same type.

To save a plot template, click on the “All plots” or “Plot_N” icon and then on the “Save Template” icon.



Figure 54: Save Template Icon

The next time the user opens the data plotter buffer, the plot templates will be automatically loaded in the “Plot Templates” box and the related plots available for visualization.

5.2. Plot settings

Plot settings are easily configurable.

Plot name:

Although the data container names (Plot_L, Serie_M, Data_N) are auto-generated, the user can change these names by clicking on the related icon the new desired, entering the name in the Title box and pressing enter.



Figure 55: Title renaming example

When the plot is renamed, the new name will appear on top of the plot.

NOTE: The names shall be different between all chart panels otherwise the references to the panels will be lost. This issue will be corrected on future release of SDV.

Plot color:

The user can also change the plot color, clicking on the Serie_N icon, the color menu appears.



Figure 56: color setting menu

Clicking on the Browse tab allows the user to select a color from the color table.

When setting the title color, the following dialog appears:




Figure 57: Plotter properties color setting

Select a color by clicking on one of color boxes. Then press OK to set the title to the selected color.

Clicking on the HSB tab, the following dialog appears:




Figure 58: Plotter HSB color setting

The user can then set HSB color components by clicking in the H, S, or B menu box. To select the appropriate value, the user must maintain the left mouse button pressed on the cursor and drag it up or down.

Clicking OK will apply the color settings to the title.

Clicking on the RGB selection box will cause the following menu to appear:




Figure 59: Plotter RGB color setting

The user can then set the RGB components of the color by dragging the RGB cursors using the mouse button.

Clicking Ok will apply the color settings to the title.

Zoom in / Zoom out:

It is possible to “Zoom-In” on a graph by clicking in the graph pane, maintaining the left mouse button clicked and dragging the mouse cursor down and to the right. The zoom-out can be performed dragging the mouse cursor upwards and to the left while maintaining the left mouse button clicked in.

6. L1A SPECIFIC VISUALIZATION FEATURES

This section presents the L1A specific visualization features implemented by SMOSView. There are two L1A visualization features: the L1A visibility matrix and the star domain representation. The L1A specific visualization features apply only to the following L1A products:

L1A products
SM_XXXX_MIR_AFWD1A
SM_XXXX_MIR_AFWU1A
SM_XXXX_MIR_CRSD1A
SM_XXXX_MIR_CRSU1A
SM_XXXX_MIR_FWSD1A
SM_XXXX_MIR_FWSU1A
SM_XXXX_MIR_SC_D1A
SM_XXXX_MIR_SC_F1A
SM_XXXX_MIR_TARD1A
SM_XXXX_MIR_TARF1A
SM_XXXX_MIR_UAVD1A
SM_XXXX_MIR_UAVU1A
SM_XXXX_MIR_UNCD1A
SM_XXXX_MIR_UNCU1A

Table 3: L1A products to which L1A Specific Visualization Features apply

6.1. L1A visibility matrix

In order to use the L1A visibility matrix, the user must select first a L1A product file using the File Chooser buffer as presented in section 4.1 of this document.

The user can then click on the SMOS Specific Visualization Features Icon, the following window appears:




Figure 60: L1A visibility matrix example

6.2. What the plot shows

The plot shows four rectangular matrixes representing the complex data displayed in the Data Field drop down menu, in this case CALIB_VISIB. The plot corresponds to the L1A calibrated visibilities presented in the SMOS Level 1 and Auxiliary Data Products Specifications. The plots show:

- Upper left plot: Real part of the complex L1A data
- Upper right plot: Imaginary part of the complex L1A data
- Lower left plot: Amplitude of the complex L1A data
- Lower right plot: Phase of the complex L1A data

Four rectangular matrixes are displayed, one matrix per real / imaginary / amplitude or phase of the complex number selected by the drop-down menu of the selector field. The lower part of each matrix is filled out with the complex conjugate part of the upper part. Each value extracted from the product is represented using a grey level scale.

NOTE:

In the case of CRSx1A products, the Amplitude matrix shows the consolidated averaged FWF Origin amplitude (**Cons_Ampl_FWF-Origin**), and shall consist of 1 data set record. This structure shall

contain the complete set of calibration parameters for every pair of receivers, expressed as a real value (FWF Origin amplitude only).

The Phase matrix shows the **Cons_Phase_FWF_Origin** structure consisting in a number of data set records with parameters obtained after correlated noise injection in odd and even sources during FWF Origin or Local Oscillator Calibration Sequences. There shall be as many Data Set Records as LO Phase Tracking events plus FWF Origin Sequences.

User will be able to navigate through all the phase measurements, however the Amplitude shall remain constant.

6.2.1. Features available

6.2.1.1. Zoom in / Zoom out:

It is possible to “Zoom-In” on a graph by clicking in the graph pane, maintaining the left mouse button clicked and dragging the mouse cursor down and to the right. The zoom-out can be performed dragging the mouse cursor upwards and to the left while maintaining the left mouse button clicked in.

6.2.1.2. Hide parameters to magnify visualized data:

Each feature has such a magnifying glass sign before: . The user can hide/unhide the functionality's parameters by clicking on this magnifying glass. It allows the user to save space on the screen to better observe the data. When the functionality's parameters are hidden the icon slightly turns: 

6.2.1.3. Plot Type




Figure 61: Plot Type drop down menu

The user can select two different plot types using this drop down menu, Square Matrix or Star Domain visualization.

6.2.1.4. Snapshot and title settings




Figure 62: Snapshot setting details

Snapshot settings give information concerning the current snapshot to the user:

- Universal Time Coordinated (UTC) of the snapshot
- Polarization of the snapshot (H: Horizontal, V: Vertical)
- Data field: plotted data fields are predefined. In the case of MIR SC D1A, the L1A specific visualization features, only the data field CALIB_VISIB is available. But the user can select a UNC 1A product. In this case, the Data field drop down menu offers two predefined data fields to be visualized using the L1A specific visualization features: MEAN_OFFSETS and UNC_OFFSET_CORRECTION. The user simply needs to click on the data fields he wants to visualize.




Figure 63: Data field drop down menu example

- Title settings: allow the user to overwrite the title displayed above the real, imaginary, amplitude, and phase matrices. It is useful especially to export these matrices towards various formats (see next paragraph).

In the release 1.6.0 of SDV it has been included in this panel further more information regarding the product.

☐ **MIR_UAVx1A**

Start_Time, Stop_Time, Correlator_Layer, Samples, Software_Error_Counter,
Instrument_Error_Counter, ADF_Error_Counter, Calibration_Error_Counter

☐ **MIR_CRSx1A**

Start_Time, Stop_Time, Correlator_Layer, Samples, Time_From_ANX ,Software_Error_Counter,
Instrument_Error_Counter, ADF_Error_Counter, Calibration_Error_Counter

☐ **MIR_SC_x1A / MIR_TARx1A**

Snapshot_Time, Snapshot_ID Snapshot_OBET , Antenna_Boresight, Max_Mkj_module, X –Band, Software_Error_flag, Instrument_Error_flag, ADF_Error_flag, Calibration_Error_flag

❑ MIR_SC_x1B / MIR_TARx1B

Snapshot_Time, Snapshot_ID Snapshot_OBET, Antenna_Boresight, X –Band, Software_Error_flag, Instrument_Error_flag, ADF_Error_flag, Calibration_Error_flag

6.2.1.5. Value details




Figure 64: Value Details display

When the user drags the mouse over the plot, the complex values corresponding to the point under the mouse cursor are displayed in the Value Details box.

R: real part; I : Imaginary part; M: Magnitude (Amplitude); P: Phase.

X and Y are the line and column number.

6.2.1.6. Export

The user can use the Export box to export the displayed screen in various image, postscript, or PDF formats.



Figure 65: Export Box

Click on “Export”. An export format box opens (Figure: 66); then select the path and name of the file to be created, and the format to which you would like to export the matrices. An example of the JPG result is given in Figure 67.




Figure: 66 Export formats




Figure 67: JPG export result

The user can step through the product and visualize consecutive snapshots contained inside the product, as explained at the end of this section. One way of identifying snapshots is the OBET, associated with a snapshot.

6.2.1.7. Colour Table

The matrix values are displayed using a grey level scale, but the user can use color tables to display matrixes using false color. Clicking on the Color Tables tab in each matrix will display a predefined selection of color tables:




Figure 68: Color Tables menu



Figure 69: Color table example

Clicking on the selected color table will assign the selected color table to the plot. The matrix plot is then updated.




Figure 70: L1A matrix representation using a color table

The user can visualize the color scale just next to the plot, by ticking the box “**Display color scale in plot**”. As shown in Figure 71, the color scale appears on the right of the plot with the range of values. The user can display or not this color scale in the plot by ticking / unticking the option. It allows the user to save screen space to visualize the data.



Figure 71: “Display color scale in plot” selected

The user can also select the **minimum and maximum** of the range to be displayed within the color table:

- by moving the sliders located above and below the table color or
- by entering new minimum and maximum values in the box and pressing “Enter”
- by entering new minimum and maximum values and selection “Scale” option. This way the color values will be redefined according to the user defined range instead of the minimum and maximum of the product.

An example of the same matrix than above is given in Figure 72, instead of the whole range [-6.427; 2.978], only the values between 1 and 2 (see color scale in plot) are displayed within the whole dynamic of the color scale.




Figure 72: Min and max color scale range selection

6.2.1.8. Stepping through the product

The user can step through the data product and plot the next snapshot using the slider at the bottom of the plot. The user can also use the two buttons “-“ / “+” to step through the product and visualize consecutive snapshots.



Figure 73: Snapshot slider

To use the slider, click with the left mouse button on the slider, maintain the button clicked and drag the mouse cursor along the slider bar. To use the - / + buttons to step through the product and see consecutive snapshots, click on the – or + buttons.

6.3. L1A Star Domain

Using the Plot Type tab, select the Star Domain visualization, the following plot appears:




Figure 74: Start Domain visualization example

The plot shows Start Domain representation of the selected Data Field (in this case CALIB_VISIB).

The features available for the “star domain visualization” are the same as the ones available for the “square matrix” representation:

- Zoom in / Zoom out: see page 62
- Hide parameters to magnify visualized data: see page 62

Functions on the left hand side pane are the same:

- Plot Type: see page 62(To Change to Spatial Representation)
- Snapshot and title settings: see page 63
- Value details: see page 64
- Export to image or postscript formats: see page 64

The Colour Table function under each plot is also the same: see page 65.

The Stepping through the product with the **Snapshot slider** is also the same: see page 68.

7. L1B SPECIFIC VISUALIZATION FEATURES

This section presents the L1B specific visualization features implemented by SMOSView. There are two L1B visualization features:

- the Fourier components of Brightness Temperature (BT) representation (or L1B star domain)
- the reconstructed BT (or L1B spatial representation)

The mathematical details associated with these representations are fully detailed in the SMOSView specification document. The L1B specific visualization features apply only to the following L1B products:

L1B products
SM_XXXX_MIR_SC_D1B SM_XXXX_MIR_SC_F1B SM_XXXX_MIR_TARD1B SM_XXXX_MIR_TARF1B

Table 4: L1B products to which L1B Specific Visualization Features apply

7.1. L1B Fourier Components of Brightness Temperature

In order to visualize the Fourier components of BT, the user must select first a L1B product file using the File Chooser buffer as presented in section 4.1 of this document.

The user can then click on the SMOS Specific Visualization Features Icon , the following window appears:




Figure 75: L1B Fourier Components of BT example

This plot is of the same type as the Star Domain plot for L1A.

The controls associated with this plot are the same than the previous ones:

- Zoom in / Zoom out: see page 62
- Hide parameters to magnify visualized data: see page 62

Functions on the left-hand side pane are the same:

- Plot Type:
- For L1B data, the plot type menu allows the user to switch between Fourier Components of BT representation and the spatial reconstructed BT:




Figure 76: L1B Plot type menu

- Snapshot and title settings: see page 63
- Value details: see page 64
- Export to image or postscript formats: see page 64

The Colour Table function under each plot is also the same: see page 65.

The Stepping through the product with the **Snapshot slider** is also the same: see page 68.

7.2. L1B Reconstructed Brightness Temperature

Using the Plot Type menu, the user can select the Spatial Representation of L1B: “Reconstructed_BT”. This plot type is not a simple visualization of L1B data but show features that have been derived from the L1B data by a procedure described in Appendix C.




Figure 77: L1B Spatial Representation example

The reconstructed BT plot type shows four hexagonal spatial representations of the L1B complex data field displayed in the Snapshot Settings box.

The controls associated with this plot are the same than the previous ones:

- Zoom in / Zoom out: see page 62

- Hide parameters to magnify visualized data: see page 62

Functions on the left hand side pane are the same:

- Plot Type: see page 71
- Snapshot and title settings: see page 63
- Value details: see page 64
- Export to image or postscript formats: see page 64

The Colour Table function under each plot is also the same as for L1A: see page 65.

The Stepping through the product with the **Snapshot slider** is also the same: see page 68.

8. L1C SPECIFIC VISUALIZATION FEATURES

This section presents the L1C specific visualization features implemented by SMOSView. The L1C specific visualization features apply only to the following L1C products:

L1C products	
SM_XXXX_MIR_SCLD1C SM_XXXX_MIR_SCSD1C	<i>Dual Polarization reconstructed BT swath</i>
SM_XXXX_MIR_SCLF1C SM_XXXX_MIR_SCSF1C	<i>Full Polarization reconstructed BT swath</i>
SM_XXXX_MIR_BWLD1C SM_XXXX_MIR_BWLF1C SM_XXXX_MIR_BWSD1C SM_XXXX_MIR_BWSF1C	<i>Browse BT products</i>

Table 5: L1C products to which L1C Specific Visualization Features apply

Note from the SMOS Level 1 and Auxiliary Data Products Specifications:

- ❑ The **dual** polarization reconstructed brightness temperature swaths are L1C products obtained from L1B products in **dual** polarization mode. It is organized in grid points (belonging to the Digital Global Grid DGG).
- ❑ The **full** polarization reconstructed brightness temperature swaths are L1C products obtained from L1B products in **full** polarization mode. It is organized in grid points (belonging to the Digital Global Grid DGG).
- ❑ The **Browse** Brightness Temperature L1 data products are arranged in pole-to-pole swaths according to ascending and descending passes. Each grid point contains a brightness temperature sample interpolated from MIRAS measurements at an incidence angle of 42.5°.
- ❑ The values of the Incidence Angles, Azimuth Angle, Faraday Rotation Angle and Geometric Rotation Angle are now presented in Engineering units in the Browser and also in the Visualization panel.

8.1. L1C Dual polarization visualization

In order to use the L1C Dual polarization specific visualization features, the user must select first a L1C dual polarization product file using the File Chooser buffer as presented in section 4.1 of this document.

The user can then click on the SMOS Specific Visualization Features Icon , the following window appears:




Figure 78: L1C Specific Visualization Feature Window

8.1.1. Plot type

On the left panel, there are several controls. The upper left one is the plot type. For L1C products, there are two options: Pixel Attributes Projection or Measurement Counter Projection, as shown in the Plot type menu below:




Figure 79: L1C Plot Type Menu

In case of Pixel Attributes Projection, it is possible to select the field to be plotted, and to request its projection for a given snapshot or for a given range of incidence angle. The relevant field to be plotted has to be chosen from the "Attributes" menu (see Figure 80), the snapshot has to be selected from the snapshot ID selector (see Figure 89), the incidence angle range has to be chosen from the incidence angle selector (see Figure 90).

In case of Measurement Counter Projection, there is no selection of incidence angle nor snapshot. The value displayed gives the number of snapshots in the product over each grid point.

8.1.2. Pixel Attributes Projection

WARNING: For big products (around 250 Mb) the time needed to project the data is quite long... Please be patient!

8.1.2.1. Attributes

By default, the selected plot type is pixel attributes projection. It allows the user to visualize all the following L1C fields projected on the Earth map:

- FLAGS: indicate the polarization (H: Horizontal, V: Vertical),
- SNAPSHOT_ID: Unique identifier for the snapshot,
- BTVALUE: Brightness Temperature value over the current Earth fixed grid point (in K),
- RAD_ACC PIX: pixel radiometric accuracy
- Azimuth angle (0° if local North)
- Incidence Angle (0° if vertical)
- FARADY ROT ANGLE: Faraday Rotation Angle
- GEO ROT ANGLE: Geometric Rotation Angle
- Footprint axis 1: Elliptical footprint major semi-axis value.
- Footprint axis 2: Elliptical footprint minor semi-axis value.
- Footprint ratio: Ratio between footprint axis 1 and footprint axis 2.

Even if selected by default, to visualize such parameters projected on the Earth, the **user must select it by the “Attributes”** drop down menu:




Figure 80: L1C Attributes Drop Down Menu

The value of the selected attribute is given inside the main pane in a little box next to the pixel covered by the mouse and the value is updated (with a less than 1 second refreshing time) when the mouse moves. After some 4 seconds over the same pixel, the value and the little box disappear, they can be visualized again by moving the mouse. See example in Figure 81.

All the pixels displayed in this figure refer to the same snapshot selected from the GUI.

The values of the field plotted correspond to the polarization of the snapshot. The polarization of the product is displayed lower part of the window, below the Snapshot ID.




Figure 81: Example of L1C BT value field displayed. All pixels displayed refer to the same snapshot (100619).

8.1.2.2. Geo Tools

When the mouse is moving through the projected data, the “Geo Tools” give the user useful geographical information about the current mouse position: Latitude, longitude, and about the grid information: Grid ID, grid latitude, grid longitude, and grid mask.

Note: the latitude/longitude grid information gives the position of the center of the grid ID, while the “geo info” gives the exact cursor latitude/longitude.




Figure 82: L1C Geo Tools Box Details

8.1.2.3. Projections

The default projection used is the Mercator projection. However, it is possible to visualize the data through other geographical projections such as Orthographic (North/South) or Gnomonic projections. For example, if data are located northern than 50° latitude North or southern than 50° latitude South, it is much more suitable to use a North/South Orthographic projection (see Figure 84). The projection can be selected through the Projections drop down menu:




Figure 83: Projections Drop Down Menu




Figure 84: North Orthographic projection example

8.1.2.4. Colour Tables and Range

The L1C products are displayed using a grey level scale, but the user can use colour tables to display L1C product using false colour. Clicking on the Colour Tables tab will display a predefined selection of colour tables:




Figure 85: Colour Tables Menu

Clicking on the selected colour table will assign the selected colour table to the plot. The plot is then updated.

The colour range is loaded by default with the Min and Max values calculated directly from the points displayed on the map, however the user can set those values using the Min and Max text fields and then clicking on the “Scale” tick box. Afterwards the points are redisplayed according to the new range.

8.1.2.5. Export

The user can use the Export box to export the displayed screen in various image, postscript, or PDF formats.

Click on “Export”. An export format box opens (Figure 86); then select the path and name of the file to be created, and the format to which you would like to export the matrices. An example of the JPG result is given in Figure 87.



Figure 86: Export Box




Figure 87: Export formats drop down menu

8.1.2.6. Zoom in / out / around

It is possible to “Zoom In” or “Zoom out” on the product, and to move in each direction by using the zoom in / out/ around tool (Figure 88):

- Zoom in: use the (+) magnifier (upper one) OR without the tool: directly in the graph pane maintain the left mouse button clicked and drag the mouse cursor down and to the right
- Zoom out: use the (-) magnifier (lower one)
- Go to the North / South: use the upper / lower arrow
- Go to the West / East: use the left / right arrow
- Center the plot on 0° latitude; 0° longitude: click on the point in the center of the tool.
- Center the plot on a point within the map: left-click once over the desired center




Figure 88: L1C Zoom in / out / around Tool

8.1.2.7. Snapshot ID selector

The user can step through the data product and plot the next snapshot using the snapshot IF slider at the bottom of the plot (Figure 89). The user can also use the two buttons “-“ / “+” to step through the product and visualize consecutive snapshots. The user can also visualize only the data corresponding to the polarization of choice. Values for full polarization products are: HH, VV, HV_Real and HV_Img. Values for dual polarization products are HH and VV.




Figure 89: L1C Snapshot ID selector box

8.1.2.8. Polarization

The polarization information is given inside the snapshot ID selector box. For L1C dual product, the polarization can be HH or VV.

8.1.2.9. Incidence angle selector

The user can select a range of incidence angle (0° if vertical incidence) by filling the L1C incidence angle selector (Figure 90). The unit of the angle selector is millidegree (10^{-3} degree), it means the same unit used inside the product. To define the incidence angle range, the user must enter a minimum, a maximum value and the “central value”. In case multiple values fit inside the [min, max] range for a single pixel, the application will choose the data that are the nearest to the central value. To display only the data acquired with an incidence angle within the range, the user has then to click on “Display”.

Additionally, the user can narrow down the number of points to visualize by selecting the desired polarization. Values for full polarization products are: HH, VV, HV_Real and HV_Img. Values for dual polarization products are HH and VV.

Once the user has selected an incidence angle range, the image will display all the pixels of the file having the incidence angle within the range.




Figure 90: L1C Incidence Angle Selector

8.1.3. Measurement Counter Projection

WARNING: For big products (around 250 Mb) the time needed to project the data is quite long... Please be patient!

If the user selects the “Measurement Counter Projection” plot type, he will then visualize the field “Counter” of the Swath_Snapshot_List data set. The field “Counter” specifies the number of Data Set Record contained in it.

The value displayed in the small box when moving the mouse over the product gives the number of snapshots in the product over each grid point. An example of such a counter is given in Figure 91.




Figure 91: Measurement Counter Projection L1C example

Note: The lower control pane for “Measurement Counter Projection” plot type only has the zoom in / out / around control.

8.2. L1C Full polarization visualization

In order to use the L1C Full polarization specific visualization features, the user must select first a L1C Full polarization product file using the File Chooser buffer as presented in section 4.1 of this document.

The user can then click on the SMOS Specific Visualization Features Icon , to use these features.

The L1C full polarization visualization features are exactly the same as the ones described in the previous L1C dual polarization specific visualization features section. Please refer to section 8.1.

8.2.1. Polarization

The only parameter that changes compared to L1C dual product is the polarization. This information is also given inside the snapshot ID selector box. For L1C full product, the polarization can be HH, VV, HV_real or HV_imaginary.

8.2.1.1. Brightness Temperatures Specific Plot

Once a brightness temperature map is obtained there is the possibility to display a graph showing the evolution of the BT vs the incidence angle for a selected grid point. This grid point is selected through the left click of the mouse.




Figure 92: BT vs Incidence Angle Selection Menu

There is the possibility to plot three different types of charts:

1. **BT ToA:** Brightness Temperature on Top of Atmosphere vs Incidence Angle
2. **BT ToA + GR:** Brightness Temperature on Top of Atmosphere with the Geometric Rotation vs Incidence Angle.
3. **BT ToA + GFR:** Brightness Temperature on Top of Atmosphere with the Geometric Rotation and Faraday Rotation vs Incidence Angle

The of the geometric and faraday rotations where performed based on the multiplication presented below. The T3' and T4' is the real and imaginary part of the BT value present in the product. G is the geometric rotation and F the Faraday rotation angles.

- **Full Pol:**

$$\begin{bmatrix} Th \\ T3 \\ T4 \\ Tv \end{bmatrix} = \begin{bmatrix} A^2 & -2AB & 0 & B^2 \\ AB & A^2 - B^2 & 0 & -AB \\ 0 & 0 & 1 & 0 \\ B^2 & 2AB & 0 & A^2 \end{bmatrix} \times \begin{bmatrix} Txx \\ T3' \\ T4' \\ Tyy \end{bmatrix}$$

$$A = \cos(G + F) \quad B = \sin(G + F)$$

- **Dual Pol:**

$$\begin{bmatrix} T_h \\ T_v \end{bmatrix} = \frac{1}{A^4 - B^4} \begin{bmatrix} A^2 & -B^2 \\ -B^2 & A^2 \end{bmatrix} \begin{bmatrix} T_{xx} \\ T_{yy} \end{bmatrix}$$

$$A^4 - B^4 = 0.01 \Rightarrow T_h = T_{xx} \text{ and } T_v = T_{yy}$$

The graphs obtained are composed by two curves, one for the H polarization and another for the V polarization. Each curve has different colours and unique Y-axis scale to allow comparison. In the Full Polarization case two extra curves are plotted. One for the HV_real and another for the HV_imaginary also as function of the incidence angle.




Figure 93: BT vs Incidence Angle Chart

8.3. L1C browse products visualization

In order to use the L1C browse products specific visualization features, the user must select first a L1C browse product file using the File Chooser buffer as presented in section 4.1 of this document. The user can then click on the SMOS Specific Visualization Features Icon , the L1C browse products visualization window opens. Figure 94 shows a L1C browse product for which the North orthographic projection has been selected and a “blue-red” colour table chosen):




Figure 94: L1C browse product visualization example (North orthographic projection)

Note that for browse products, the controls in the lower pane are slightly different than the dual/full polarization ones. There is no incidence angle selection (all browse products have the same incidence angle) nor snapshot_ID selection.

The controls in the lower panel deal with:

- Zoom in / out / around tool (see page 80).
- Polarisation selector: allow the user to visualize products only from the selected polarization (select the required polarization with the drop down menu).

WARNING: For big products (around 250 Mb) the time needed to project the data is quite long... Please be patient!

9. L2 SPECIFIC VISUALIZATION FEATURES

This section presents the L2 specific visualization features implemented by SMOSView. The L2 specific visualization features apply only to the following L2 products:

L2 products
SM_XXXX_MIR_OSUDP2 SM_XXXX_MIR_SMUDP2

Table 6: L2 products to which L2 Specific Visualization Features apply

Except two functionalities (the selection flags and the error mode) the L2 specific visualization features apply also to auxiliary data files listed in Table 7.

WARNING: However, the user should know that due to the incredible points to project on the map, the auxiliary files could take about 30 minutes to be displayed.

Auxiliary data products
AUX_DGG___ (Geodetic Product) AUX_ECMWF (ECMWF Product) AUX_DFFLAI_ (LAI Product) AUX_DFFLMX (LAI MAX Product) AUX_DGGTLV (Current Tau Nadir LV Product) AUX_DGGTFO (Current Tau Nadir FO Product) AUX_DGGROU (Current Roughness H Product) AUX_DGGRFI_SPH (RFI Product) AUX_DGGFLO_SPH (Current Flood Product) AUX_GAL_SM_SPH (Galaxy Map Product convolved with the AUX_MN_WEF) AUX_SOIL_P_SPH (Soil Properties Product) AUX_BIGBWF_SPH (Big water body flag Product) AUX_RFI_____SPH (L1 RFI Product) AUX_GAL_OS_SPH (Galactic Map Product convolved with the AUX_WEF) AUX_DISTAN_SPH (Land Sea Mask) AUX_SSS_____SPH (SSS Climatological LUT) AUX_FARA_ (Faraday Rotation) AUX_GAL_OS (Ocean Salinity Galaxy Map) AUX_GAL_SM (Soil Moisture Galaxy Map) AUX_OTTxD/F (Ocean target transformation) AUX_DTBCUR (Current Delta TB Product) AUX_DTBXY (Delta TBs for the L2OS post-processor)

Table 7: L2 products to which L2 Specific Visualization Features apply

In order to use the L2 specific visualization features, the user must select first a L2 Soil Moisture or Ocean Salinity product file using the File Chooser buffer as presented in section 4.1 of this document.

The user can then click on the SMOS Specific Visualization Features Icon , the following window appears:




Figure 95: L2 specific visualization feature window

9.1. Controls from left pane

The controls of the control panel on the left are described hereafter:

SMOSView allows projecting all fields and their associated errors from Level 2 Ocean Salinity User Data Product (MIR_OSUDP2) and Level 2 Soil Moisture User Data Product (MIR_SMUDP2). The tables below list all these fields:

OSUDP2 Field	Description
SSS1	Sea surface salinity using roughness model 1
SSS2	Sea surface salinity using roughness model 2
SSS3	Sea surface salinity using roughness model 3
WS	Equivalent neutral wind speed as derived from ECMWF
SST	Sea Surface Temperature as derived from ECMWF
Tb_42.5H	Brightness Temperature at surface level derived with default

Tb_42.5V	forward model and retrieved geophysical parameters, H polarisation direction. Brightness Temperature at surface level derived with default forward model and Retrieved geophysical parameters, V polarisation direction.
----------	---

Table 8: L2 Ocean Salinity fields that can be projected on the geographical map

L2 SM Field	Description
Soil_Moisture	Retrieved soil moisture value
Optical_Thickness_Nad	Nadir optical thickness estimate for vegetation layer
Physical_Temperature	Surface equivalent temperature – may be a retrieved value or from an external source
TTH	Optical thickness coefficient for polarisation H
RTT	Ratio of optical thickness coefficients TTH/TTV
Scattering_Albedo_H	Scattering albedo for horizontal polarisation
DIFF_Albedos	Difference of albedos $\omega_H - \omega_V$
Roughness_Param	Roughness parameter estimate
Dielect_Const_MD_RE	Real part of the dielectric constant from MD retrieval.
Dielect_Const_MD_IM	Imaginary part of dielectric constant from MD retrieval
Dielect_Const_Non_MD_RE	Real part of dielectric constant from retrieval models other than MD
Dielect_Const_Non_MD_IM	Imaginary part of dielectric constant from retrieval models other than MD
TB_ASL_Theta_B_H	Surface level TB (corrected from sky/atmosphere contribution) computed from forward model with specific incidence angle θ_B (42.5 °), and for H polarisation.
TB_ASL_Theta_B_V	Surface level TB (corrected from sky/atmosphere contribution) computed from forward model a specific incidence angle θ_B (42.5 °), and for V polarisation
TB_TOA_Theta_B_H	Top of the atmosphere TB computed from forward model at specific incidence angle θ_B (42.5°), for H polarisation
TB_TOA_Theta_B_V	Top of the atmosphere TB computed from forward model at specific incidence angle θ_B (42.5°), for V polarisation

Table 9: L2 Soil Moisture fields that can be projected on the geographical map

9.1.1. Field selection

A field selection drop down menu allows the user to select the field to project on the map as shown in Figure 96. Even if selected by default, to visualize such parameters projected on the Earth, the **user must select the field to be projected on the map by the “Field selection” drop down menu:**




Figure 96: Field selection box (OS product on the left; SM product on the right)

9.1.2. Flags selection

The user can select one or more flags available from the L2 product and overlay them to the displayed product. The available flags for the chosen product can be visualized in the flags selection box, as displayed in Figure 97.




Figure 97: Flags selection box

To select a flag to be overlaid to the image, the user must click in the left column box of the flag. The colour of the flag and the transparency are configurable.

To choose the color and the transparency of the flag to display the user must click in the second column starting left. The following menu is then displayed:




Figure 98: Flags color transparency menu

The user can choose the color of the flag in the “Swatches” tab: by clicking on the desired color (see Figure 98). He can then select the transparency level in the “Transparency selection” tab: by moving the slider to the transparency level desired (see Figure 99).

NOTE: Due to the use of a different point layer to display flags in the world map, sometimes during the zoom operations they may appear outside of the original position. In this case the zoom shall be performed prior to the display of the flags.




Figure 99: Flags transparency selection menu

9.1.3. Geo Tools

When the mouse is moving through the projected data, the “Geo Tools” give the user useful geographical information about the current mouse position: Latitude, longitude, and about the grid information: Grid ID, grid latitude, grid longitude, and grid mask.

Note: the latitude/longitude grid information gives the position of the center of the grid ID, while the “geo info” gives the exact cursor latitude/longitude.

See Figure 82.

9.1.4. Projections

The default projection used is the Mercator projection. However, it is possible to visualize the data through other geographical projections such as Orthographic (North/South) or Gnomonic projections. See more details in section 8.1.2.3.

9.1.5. Field color Scale

The user can select the color table that will be affected to the field to be projected thanks to the Field color scale. The user has to select a color table within the drop down menu of Figure 100.




Figure 100: L2 field color scale

The colour range is loaded by default with the Min and Max values calculated directly from the points displayed on the map, however the user can set those values using the Min and Max text fields and then clicking on the “Scale” tick box. Afterwards the points are redisplayed according to the new range.

9.1.6. Example

Once the field, the color tables and the projections selected, the following window displays the L2 data on the geographical map:




Figure 101: L2 OS product visualization example

9.2. Error mode

L2 specific visualization features include an “error mode” that allows the user to display and project on the map the associated error contained in the L2 product (e.g. DQX) to the field selected (e.g. soil moisture), above the field itself. To use the error mode, the user has to choose the error mode by clicking on the “Error mode” icon below the main panel:




Figure 102: Click on the “Error Mode” icon to start the error mode

Once displayed, the user can as previously navigate through the projected data using the zoom in / out / around tool of Figure 102.

9.2.1. Error color scale

The color scale of the error displayed above the field projected can be chosen among various color tables thanks to the “Error color scale” drop down menu:




Figure 103: Error color scale

9.2.2. Error mode example

To use the error mode, the user has first to project one field using the features of the previous section “Field selection”, page 89.

Once the error mode selected and the colour table selected, the user can simply left-click on the area where he would like the error to be displayed above the projected data. The error is then displayed above the data, all around the clicked position as seen in Figure 104 hereafter.




Figure 104: Error mode display above SSS field

9.2.3. Visualization Approach on AUX_SSS and AUX_DISTAN

Due to the fact that this AUX_SSS and AUX_DISTAN files have a huge number of points (cover the whole DGG grid) and SMOS View visualization plugin memory limitations don't allow the simultaneous display of a so large number of points, the display of data is performed zone by zone. In total there are 6 zones available

A new panel was created below the world map containing the available zones.




Figure 105: AUX_SSS Zone Panel Dummy Data Filtering

Some SMOS products like L2 and AUX are filled with dummy data, which is initialization values that are kept in the final product. In most of the cases those values don't have an important meaning, therefore it was found the need of don't display them in the world map.

The values considered as dummy are the following:

- ☐ -999
- ☐ -99999
- ☐ -99998

By default, the specific visualization feature doesn't consider these values on the world map, however the user is able to display them.

To display the dummy values on the world map the user must select the option "Display DUMMY Values" present on the "Tools" panel, located below the world map.




Figure 106: Display DUMMY Values Option

The values are then displayed in the world map with colour "Black", in order to clearly identify them, the colour scale shall be different than the "Black and White", if for some reason the "Black and White" scale its set it should be changed to another that doesn't contains the black colour. The dummy values are then added and shown within the values layer. If the user unselects the option, then world map will be repainted without the dummy values.

9.2.3.1. Visualization Approach for the AUX_SSS for schema version 400

For the new schema version 400 a new visualization panel was implemented for the AUX_SSS product. With this new panel the user can plot the monthly values, divided into 6 zones, for the following parameters: SSa, SSa-quality, SSb and SSB_quality for each LUT A and D.




Figure 107: AUX_SSS product visualization for a product schema version 400

9.2.4. Visualization of AUX_FARA Products

The main purpose of this ADF is to provide the L2OP with a more precise computation of the Faraday angle based on algorithm improvements and refined VTEC background field (i.e. the combined VTEC). In addition, the Faraday rotation auxiliary file can be used in any of the DPGS sub/system, and allows de-coupling L1 reprocessing activity for algorithm upgrades and availability of a more precise Faraday rotation (i.e., VTEC combined, usage of refined geomagnetic model). This ADF has the following types:

- AUX_FARA_C (Consolidated Faraday Rotation)
- AUX_FARA_P (Predicted Faraday Rotation)
- AUX_FARA_R (Rapid Faraday Rotation)

SMOS Data Viewer provides the possibility for the user to perform a specific visualization in a panel similar to L1C (snapshot by snapshot basis) but without the polarization filter. The following figure presents a screenshot of a visualization showing on the left side the variables available for the user.




Figure 108: AUX_FARA Specific Visualization

9.2.5. Visualization of AUX_GAL_OS and AUX_GAL_SM

The specific visualization of AUX_GAL_OS and AUX_GAL_SM is performed on a (Ra, De) chart with 721x1441 elements. On the AUX_GAL_OS the chart will display the corresponding TB_Sky_H (Sky TB for Horizontal Polarization) and TB_Sky_V (Sky_TB for Vertical Polarization) values for each Right Ascension (Ra), Declination (De) pair of coordinates.

For the AUX_GAL_SM the visualization panel is divided in four charts:

- ☐ I_CSWeF (First Stokes Parameter)
- ☐ Q_CSWeF (Second Stokes Parameter)
- ☐ U_CSWeF (Third Stokes Parameter)
- ☐ Delta_I (Potential Error Due to Strong Noise Sources)

Due to jFreeChart limitations the Ra and De coordinates have a step of 0,5. The Ra ranges are from 0.0 to 360.0 while the De are from -90.0 to 90.0.

It must be noted that due to performance issues, the zoom and colour scale operations are performed slowly.




Figure 109: AUX_GAL_OS Specific Visualization




Figure 110: AUX_GAL_SM Specific Visualization

9.2.6. Visualization of AUX_OTTxD/F

The specific visualization of AUX_OTT data is performed on (Xi, Eta) charts divided by ascending and descending orbit. The visualization panel is divided in four plots, the two on the left have the Ascending orbit and the two on the right the Descending orbit.

The values shown on the “**Value Details**” panel are according to the organization of the visualization panel.

By default, the colour scale range is set to [-10.0, 10.0], if the user uncheck the “Scale” option the scale range will be set to the minimum and maximum values of the plots.

For dual polarization products the only four plots displayed are:

- ☐ LUT_offset_HH_A on the top left panel.
- ☐ LUT_offset_HH_D on the top right panel.
- ☐ LUT_offset_VV_A on the bottom left panel.
- ☐ LUT_offset_VV_D on the bottom right panel.

The following picture shows the visualization panel for the dual polarization product.




Figure 111: AUX_OTT Dual Pol Specific Visualization

For the Dual Polarization case the user can select the following polarization filters:

- ☐ HH VV
 - Same plots as the dual polarization case
- ☐ HH_short VV_short
 - LUT_offset_HH_short_A on the top left panel.

- LUT_offset_HH_short_D on the top right panel.
- LUT_offset_VV_short_A on the bottom left panel.
- LUT_offset_VV_short_D on the bottom right panel.

□ HH HH_short

- LUT_offset_HH_A on the top left panel.
- LUT_offset_HH_D on the top right panel.
- LUT_offset_HH_short_A on the bottom left panel.
- LUT_offset_HH_short_D on the bottom right panel.

□ VV VV_short

- LUT_offset_VV_A on the top left panel.
- LUT_offset_VV_D on the top right panel.
- LUT_offset_VV_short_A on the bottom left panel.
- LUT_offset_VV_short_D on the bottom right panel.

□ T3_HHV T4_HHV

- LUT_offset_T3_HHV_A on the top left panel.
- LUT_offset_T3_HHV_D on the top right panel.
- LUT_offset_T4_HHV_A on the bottom left panel.
- LUT_offset_T4_HHV_D on the bottom right panel.

□ T3_VVH T4_VVH

- LUT_offset_T3_VVH_A on the top left panel.
- LUT_offset_T3_VVH_D on the top right panel.
- LUT_offset_T4_VVH_A on the bottom left panel.
- LUT_offset_T4_VVH_D on the bottom right panel.

9.2.7. Visualization of AUX_DTBCUR

The specific visualization of AUX_DTBCUR data is performed on (Xi, Eta) charts divided in four plots, XX, YY (top) and XX Short, YY Short (bottom). The user can select other polarization filter (XY) where the four plots will be XXY Stokes 3 and XXY Stokes 4 (top), YYX Stokes 3 and YYX Stokes 4 (bottom).

Apart from the polarization, the user can select as well the orbit, model and variable (count_deltaTB, deltaTB, std_deltaTB or flags) to plot.

The values shown on the “**Value Details**” panel are according to the organization of the visualization panel.

By default the colour scale is range is “Blue-White-Red” and the range is set to [-10.0, 10.0], if the user uncheck the “Scale” option the scale range will be set to the minimum and maximum values of the plots.




Figure 112: AUX_DTBCUR Specific Visualization

9.2.8. Visualization of AUX_DTBXY

The specific visualization of AUX_DTBXY can be performed through three different panels selected by the user on the Graphics Type box:

- ☐ **Plot Panel** (Default): Showing the OTTs as it is done for the AUX_DTBCUR.
- ☐ **World Map Panel**: Showing the Snapshot through a ground track representation.
- ☐ **Charts Panel**: Show the A3TEC variables through four X-Y plots.

Introduced in version 1.8.5 of the SMOS Data viewer the user has new options to visualize the data for AUX_DTBXY products with a schema version 401. The specific visualization of AUX_DTBXY can be performed through three different panels selected by the user on the Graphics Type box:

- ☐ **World map TB bias Panel**: Showing the TB Snapshots through a ground track representation.
- ☐ **World map GeoPhy Panel**: Showing the Geo-physical through a ground track representation.

9.2.8.1. Plot Panel

Please refer section 9.2.7. Only available for AUX_DTBXY products up to with a schema version equal or below 300.

9.2.8.2. World Map Panel

On this panel the user is able to see several snapshot variables over the world map. The user can select the Region ID, FOV Zone, Polarization and Model. The supported variables are meas_count, delta_TB, model_TB and flags. Only available for AUX_DTBXY products up to with a schema version equal or below 300.




Figure 113: AUX_DTBXY World Map

9.2.8.3. Charts Panel

In this specific visualization the user is able to select the A3TEC variables (latTEC, l1cTEC, tecres, signpost) to be plotted against fovLatitude (top-left), fovLongitude (top-right), geoLatitude (bottom-left), geoLongitude (bottom-right). Only available for AUX_DTBXY products up to with a schema version equal or below 300.




Figure 114: AUX_DTBXY Charts Panel

9.2.8.4. World map TB bias Panel

On this panel the user can see several snapshot variables over the world map. The supported variables are:

- Measurement_Count
- L1cTEC
- TB_biasL1TEC
- TB_biasA3TEC

Where the TB_biasL1TEC is determined with this computation:

$$TB_biasL1TEC = L1c_Stokes_Stats.L1c_Stats.L1cTB - TOA_L1cTEC_Model_Stokes.sumTB$$

and the TB_biasA3TEC like so:

$$TB_biasA3TEC = L1c_Stokes_Stats.L1c_Stats.L1cTB - TOA_A3TEC_Model_Stokes.sumTB$$




Figure 115: AUX_DTBXY World map TB bias Panel

9.2.8.5. World map GeoPhy Panel

On this panel the user can see several Geo Physical snapshot variables over the world map. The supported variables are:

- SSS
- std_SSS
- SST
- std_SST
- WS
- std_WS
- A3TEC
- std_A3TEC
- Tair
- std_Tair
- SP
- std_SP
- TCWV
- std_TCWV
- HS
- std_HS




Figure 116: AUX_DTBXY World map GeoPhy Panel

The list of zones available for the user to choose from are listed below:

- Border
- Angle_45
- Angle_40
- Angle_38
- Angle_29
- Angle_0
- Antenna_02
- Antenna_04
- Antenna_06
- EAF_W
- EAF_SW
- EAF_SE
- EAF_E
- Central_NW
- Central_NC
- Central_NE
- Central_CW
- Central_CC
- Central_CE

- Central_SW
- Central_SC
- Central_SE
- Suspenders_West
- Suspenders_East
- Circle_04
- Filtered
- AFFOV
- EAFFOV
- FOV

APPENDIX A PREREQUISITE FOR PRINTING

☐ Windows, MacOS X

No particular requirements should be needed.

☐ Linux, UNIX

It is necessary to have the CUPS package installed.

This package is by default installed on most UNIXes and it is freely downloadable from the following website: <http://www.cups.org/>

APPENDIX B PHASE CALCULATIONS IN SMOS DATA VIEWER PLOTS

Phase is calculated using the `atan2` function provided by the standard Java library.

The code that executes this operation is the following:

```
if (_realPart != 0.0 || _imaginaryPart != 0.0)
    _phase = Math.atan2(_imaginaryPart, _realPart);
else
    _phase = 0.0f;
```

To comply with Enhancement 8 (ref. SO-MN-VEG-GS-0050 page 5), the value of the phase is set to 0 when real and imaginary values are 0.

The documentation of the `atan2` routine is the following:

The routine converts rectangular coordinates (x , y) to polar (r , θ). This method computes the phase θ by computing an arc tangent of y/x in the range of $-\pi$ to π . Special cases:

- If either argument is NaN, then the result is NaN.
- If the first argument is positive zero and the second argument is positive, or the first argument is positive and finite and the second argument is positive infinity, then the result is positive zero.
- If the first argument is negative zero and the second argument is positive, or the first argument is negative and finite and the second argument is positive infinity, then the result is negative zero.
- If the first argument is positive zero and the second argument is negative, or the first argument is positive and finite and the second argument is negative infinity, then the result is the `double` value closest to π .
- If the first argument is negative zero and the second argument is negative, or the first argument is negative and finite and the second argument is negative infinity, then the result is the `double` value closest to $-\pi$.
- If the first argument is positive and the second argument is positive zero or negative zero, or the first argument is positive infinity and the second argument is finite, then the result is the `double` value closest to $\pi/2$.

- If the first argument is negative and the second argument is positive zero or negative zero, or the first argument is negative infinity and the second argument is finite, then the result is the `double` value closest to $-\pi/2$.
- If both arguments are positive infinity, then the result is the `double` value closest to $\pi/4$.
- If the first argument is positive infinity and the second argument is negative infinity, then the result is the `double` value closest to $3\pi/4$.
- If the first argument is negative infinity and the second argument is positive infinity, then the result is the `double` value closest to $-\pi/4$.
- If both arguments are negative infinity, then the result is the `double` value closest to $-3\pi/4$.

Parameters:

y - the ordinate coordinate

x - the abscissa coordinate

Returns:

the *theta* component of the point (*r*, *theta*) in polar coordinates that corresponds to the point (*x*, *y*) in Cartesian coordinates.

APPENDIX C TRANSFORMATIONS PERFORMED TO SWITCH FROM L1B FOURIER COMPONENTS OF BT TO L1B RECONSTRUCTED BT

Technical note provided by Indra:

The visualization of the L1B product in (chi,eta) domain requires some transformations. The steps to be followed are these:

1. The starting point are the L1B product's fields:
 - **Scene_BT_Fourier** (field number 17), which contains the information to be plotted,
 - and **Flags** (field number 16) which contains information on the polarization of **Scene_BT_Fourier**.
2. **Scene_BT_Fourier** has several elements that varies depending on the product and polarization mode:
 1. Dual polarization product (SM_XXXX_MIR_SC_D1B or SM_XXXX_MIR_TARD1B):
 - the **Scene_BT_Fourier** field in this product has only pure polarizations, HH or VV. It has 1395 complex values and one real in the centre of the star. These are contained in the product as 2791 double elements.
 2. Full polarization product (SM_XXXX_MIR_SC_F1B or SM_XXXX_MIR_TARF1B): the **Scene_BT_Fourier** field in this product has 4 possibilities
 - HH or VV: it has 1395 complex values and one real in the centre of the star (2791 doubles totally).
 - HV_real or HV_imag: it has 2791 real values (doubles) covering all the star, either the real part of HV polarization or the imaginary part.
3. In dual polarization products it must be performed the complex conjugate of the **Scene_BT_Fourier** fields in pure polarizations to complete the star in the hexagonal domain. In case of a full polarization product instead of the complex conjugate, the real part is obtained through the 2791 real values of HV_real and the imaginary part is obtained through the 2791 real values of HV_imag.

I call this **Scene_BT_Fourier***. This follows the same order as **Scene_BT_Fourier**.
4. The resulting variable, which I call **CompleteStar_Scene_BT_Fourier**, is a list of values to be visualized in the hexagonal star domain plot (this is the variable to be visualized by feature specified in SOW's Req. SDV-T-6.1.6-120). The order and coordinates for the complete list of points in the star is specified in LUT *L1B_STARVIS_LUT.txt*.
5. The variable **CompleteStar_Scene_BT_Fourier** is the origin for the Brightness Temperature image in the (chi,eta) domain in whatever resolution (specified by **Xi_Eta_Resolution** field #64 in Table 4-28 of L1OP Specs), although obviously some transformations are needed in

between. The **CompleteStar_Scene_BT_Fourier** variable is related to the BT image by an Inverse FFT procedure.

6. In order to use standard FFT techniques, the **CompleteStar_Scene_BT_Fourier** variable must be fitted into a square matrix of the specified **Xi_Eta_Resolution**, I call this matrix **Rectangular_Scene_BT_Fourier**. To do this, the following procedure must be performed:
 - Create the variable **Rectangular_Scene_BT_Fourier** whose size is **Xi_Eta_Resolution** rows by **Xi_Eta_Resolution** columns, filled with all zeroes. There are 3 possible resolutions, 64x64, 128x128, and 256x256.
 - Use the look up table (*L1B_UV_STAR2RECT_LUT_***.txt*) to find the positions in **Rectangular_Scene_BT_Fourier** rectangular matrix on which the elements of **CompleteStar_Scene_BT_Fourier** have to be placed. First 2 columns contain the row and column indexes in the rectangular grid, the 3rd and 4th columns contain the corresponding (u,v) coordinates values, and the 5th column contains the position of the corresponding element of **CompleteStar_Scene_BT_Fourier** variable. In fact, you don't need columns 3rd and 4th, they are only included for clarification purposes.
 - Note that some of this column 5's positions values are set to -001: this must be understood as that the **Rectangular_Scene_BT_Fourier** must be kept with zero values. In fact, **Rectangular_Scene_BT_Fourier** is zero-padded rectangular version of **CompleteStar_Scene_BT_Fourier**. The hexagonal-grid variable is always the same size, the change in resolution in the rectangular-grid variable is achieved by zero-padding.
7. Once you have the rectangular-grid variable, you must perform an Inverse FFT. The L1PP project has used the FFTW library methods:

p = fftw_plan_dft_2d(nx, ny, bt_freq_matrix, bt_temp_snapshot, FFTW_BACKWARD,FFTW_ESTIMATE);

Where **nx** and **ny** are the number of rows and columns in the rectangular grid, **bt_freq_matrix** is the **Rectangular_Scene_BT_Fourier** and **bt_temp_snapshot** the resulting variable in the (chi,eta) domain, which I call from now on **Rectangular_Scene_XiEta**.

8. The variable **Rectangular_Scene_XiEta** has the same size of **Rectangular_Scene_BT_Fourier**. **Rectangular_Scene_XiEta** must be plotted against the coordinates specified in look-up tables *L1B_FFT_XIETA_LUT_***.txt*. The first 2 columns give the indexes in the rectangular matrix, and columns 3rd and 4th give the corresponding Xi and Eta positions.
9. You must plot all values in the **Rectangular_Scene_XiEta** variable, as scientists are interested in everything that is retrieved by the SMOS instrument, even if it is hardly usable with current algorithms.
10. The reconstruction in the xi,eta domain is implemented using the Blackman apodisation window, therefore the brightness temperature is calculated by the following approach:

$$T(\xi, \eta) = \frac{\sqrt{3}}{2} d^2 \sum_m \sum_n \hat{T}(u_{mn}, v_{mn}) \cdot W(u_{mn}, v_{mn}) \cdot e^{j2\pi(u_{mn}\xi + v_{mn}\eta)}$$

APPENDIX D: STAR DOMAIN VISUALIZATION

The Star Domain representation is performed based on the Square Matrix. The ordering is based on reporting only the baselines with positive v coordinate and u positive for v=0:

- ❑ The v coordinate for the upper half of the baselines goes continuously from 0 to $\sqrt{3} \cdot \text{NEL} \cdot d$, where $\text{NEL}=21$ and $d=0.875$, in incremental steps of $\sqrt{3} \cdot d/2$
- ❑ The u coordinate of the upper half of the baselines shall follow the mathematical rules defined as:
 - If $v=0$, then u goes from d to $24 \cdot d$ in incremental steps of d
 - If $v>0$ and $v \leq \sqrt{3} \cdot \text{NEL} \cdot d/2$, then u goes from $-(\text{NEL} \cdot d + v/\sqrt{3})$ to $+(\text{NEL} \cdot d + v/\sqrt{3})$ in incremental steps of d
 - If $v=\sqrt{3} \cdot (\text{NEL}+1) \cdot d/2$, then u goes from $-11 \cdot d$ to $+11 \cdot d$ in incremental steps of d
 - If $v=\sqrt{3} \cdot (\text{NEL}+2) \cdot d/2$, then u has the values $-23 \cdot d/2$, $-19 \cdot d/2$ to $+19 \cdot d/2$ in incremental steps of d and $+23 \cdot d/2$. Notice that the elements $\pm 21 \cdot d/2$ are not present.
 - If $v=\sqrt{3} \cdot (\text{NEL}+3) \cdot d/2$, then u has the values $-12 \cdot d$, $-9 \cdot d$ to $+9 \cdot d$ in incremental steps of d and $+12 \cdot d$. Notice that the elements $\pm 11 \cdot d$ and $\pm 10 \cdot d$ are not present.
 - Finally, if $v > \sqrt{3} \cdot (\text{NEL}+3) \cdot d/2$ and $v \leq \sqrt{3} \cdot \text{NEL} \cdot d$, then u goes from $-(\text{NEL} \cdot d - v/\sqrt{3})$ to $+(\text{NEL} \cdot d - v/\sqrt{3})$ in incremental steps of d

The order followed is shown in the next picture. For the 1395 element vector, the baselines shall be taken first from left to right, then from bottom to top. I.e. the first 24 elements are the ones with $v=0$ and ordered by increasing u; the next 42 elements are the ones with $v=\sqrt{3} \cdot d/2$ and ordered by increasing u (from negative to positive), and so on until the 1395 elements are covered.




Figure 117: Star Domain Representation

For the case of HV polarisation, where the vector is 2791 elements long, the complete star must be covered. In this case, the ordering shall be similar to the one adopted above. The first element shall be the zero baseline ($u=0$, $v=0$); the next 1395 elements shall be ordered like it has been described (left to right, then bottom to top); and the remaining 1395 element shall be ordered in the same way as well, but inverting the sign of the resulting u and v coordinates (i.e., it changes to ordering from right to left, then top to bottom).

APPENDIX E: BROWSE STRUCTURE OF LEVEL 0 PRODUCT ARRAYS

In order to be possible to correctly browse and plot variables for level 0 products, some changes have been made to the XIN schema to split the I Q correlations in smaller arrays. The following table presents the array index number and the corresponding correlation.

Array Index	Correlation
Correlator_Counts_1	
1	1_1-0
2	1_0-0
3	I24_1
4	I24_Q24
5	I24_I23
6	I24_I22
7	I24_I21
8	I24_I20
9	I24_I19
10	I24_I18
11	I24_I17
12	I24_I16
13	I24_I15
14	I24_I14
15	I24_I13
16	I24_I12
17	I24_I11
18	I24_I10
19	I24_I9
20	I24_I8
21	I24_I7
22	I24_I6
23	I24_I5
24	I24_I4

25	I24_I3
26	I24_I2
27	I24_I1
28	I24_0
29	I23_1
30	I23_Q24
31	I23_Q23
32	I23_I22
33	I23_I21
34	I23_I20
35	I23_I19
36	I23_I18
37	I23_I17
38	I23_I16
39	I23_I15
40	I23_I14
41	I23_I13
42	I23_I12
43	I23_I11
44	I23_I10
45	I23_I9
46	I23_I8
47	I23_I7
48	I23_I6
49	I23_I5
50	I23_I4

51	I23_I3
52	I23_I2
53	I23_I1
54	I23_0
55	I22_1
56	I22_Q24
57	I22_Q23
58	I22_Q22
59	I22_I21
60	I22_I20
61	I22_I19
62	I22_I18
63	I22_I17
64	I22_I16
65	I22_I15
66	I22_I14
67	I22_I13
68	I22_I12
69	I22_I11
70	I22_I10
71	I22_I9
72	I22_I8
73	I22_I7
74	I22_I6
75	I22_I5
76	I22_I4

77	I22_I3
78	I22_I2
79	I22_I1
80	I22_0
81	I21_1
82	I21_Q24
83	I21_Q23
84	I21_Q22
85	I21_Q21
86	I21_I20
87	I21_I19
88	I21_I18
89	I21_I17
90	I21_I16
91	I21_I15
92	I21_I14
93	I21_I13
94	I21_I12
95	I21_I11
96	I21_I10
97	I21_I9
98	I21_I8
99	I21_I7
100	I21_I6
101	I21_I5
102	I21_I4
103	I21_I3
104	I21_I2
105	I21_I1
106	I21_0
107	I20_1
108	I20_Q24

109	I20_Q23
110	I20_Q22
111	I20_Q21
112	I20_Q20
113	I20_I19
114	I20_I18
115	I20_I17
116	I20_I16
117	I20_I15
118	I20_I14
119	I20_I13
120	I20_I12
121	I20_I11
122	I20_I10
123	I20_I9
124	I20_I8
125	I20_I7
126	I20_I6
127	I20_I5
128	I20_I4
129	I20_I3
130	I20_I2
131	I20_I1
132	I20_0
133	I19_1
134	I19_Q24
135	I19_Q23
136	I19_Q22
137	I19_Q21
138	I19_Q20
139	I19_Q19
140	I19_I18

141	I19_I17
142	I19_I16
143	I19_I15
144	I19_I14
145	I19_I13
146	I19_I12
147	I19_I11
148	I19_I10
149	I19_I9
150	I19_I8
151	I19_I7
152	I19_I6
153	I19_I5
154	I19_I4
155	I19_I3
156	I19_I2
157	I19_I1
158	I19_0
159	I18_1
160	I18_Q24
161	I18_Q23
162	I18_Q22
163	I18_Q21
164	I18_Q20
165	I18_Q19
166	I18_Q18
167	I18_I17
168	I18_I16
169	I18_I15
170	I18_I14
171	I18_I13
172	I18_I12

173	I18_I11
174	I18_I10
175	I18_I9
176	I18_I8
177	I18_I7
178	I18_I6
179	I18_I5
180	I18_I4
181	I18_I3
182	I18_I2
183	I18_I1
184	I18_0
185	I17_1
186	I17_Q24
187	I17_Q23
188	I17_Q22
189	I17_Q21
190	I17_Q20
191	I17_Q19

192	I17_Q18
193	I17_Q17
194	I17_I16
195	I17_I15
196	I17_I14
197	I17_I13
198	I17_I12
199	I17_I11
200	I17_I10
201	I17_I9
202	I17_I8
203	I17_I7
204	I17_I6
205	I17_I5
206	I17_I4
207	I17_I3
208	I17_I2
209	I17_I1
210	I17_0

211	I16_1
212	I16_Q24
213	I16_Q23
214	I16_Q22
215	I16_Q21
216	I16_Q20
217	I16_Q19
218	I16_Q18
219	I16_Q17
220	I16_Q16
221	I16_I15
222	I16_I14
223	I16_I13
224	I16_I12
225	I16_I11
226	I16_I10
227	I16_I9
228	I16_I8

Array Index	Correlation
Correlator_Counts_2	
1	I16_I7
2	I16_I6
3	I16_I5
4	I16_I4
5	I16_I3
6	I16_I2
7	I16_I1
8	I16_0
9	I15_1
10	I15_Q24

11	I15_Q23
12	I15_Q22
13	I15_Q21
14	I15_Q20
15	I15_Q19
16	I15_Q18
17	I15_Q17
18	I15_Q16
19	I15_Q15
20	I15_I14
21	I15_I13
22	I15_I12

23	I15_I11
24	I15_I10
25	I15_I9
26	I15_I8
27	I15_I7
28	I15_I6
29	I15_I5
30	I15_I4
31	I15_I3
32	I15_I2
33	I15_I1
34	I15_0

35	I14_1
36	I14_Q24
37	I14_Q23
38	I14_Q22
39	I14_Q21
40	I14_Q20
41	I14_Q19
42	I14_Q18
43	I14_Q17
44	I14_Q16
45	I14_Q15
46	I14_Q14
47	I14_I13
48	I14_I12
49	I14_I11
50	I14_I10
51	I14_I9
52	I14_I8
53	I14_I7
54	I14_I6
55	I14_I5
56	I14_I4
57	I14_I3
58	I14_I2
59	I14_I1
60	I14_0
61	I13_1
62	I13_Q24
63	I13_Q23
64	I13_Q22
65	I13_Q21
66	I13_Q20

67	I13_Q19
68	I13_Q18
69	I13_Q17
70	I13_Q16
71	I13_Q15
72	I13_Q14
73	I13_Q13
74	I13_I12
75	I13_I11
76	I13_I10
77	I13_I9
78	I13_I8
79	I13_I7
80	I13_I6
81	I13_I5
82	I13_I4
83	I13_I3
84	I13_I2
85	I13_I1
86	I13_0
87	I12_1
88	I12_Q24
89	I12_Q23
90	I12_Q22
91	I12_Q21
92	I12_Q20
93	I12_Q19
94	I12_Q18
95	I12_Q17
96	I12_Q16
97	I12_Q15
98	I12_Q14

99	I12_Q13
100	I12_Q12
101	I12_I11
102	I12_I10
103	I12_I9
104	I12_I8
105	I12_I7
106	I12_I6
107	I12_I5
108	I12_I4
109	I12_I3
110	I12_I2
111	I12_I1
112	I12_0
113	I11_1
114	I11_Q24
115	I11_Q23
116	I11_Q22
117	I11_Q21
118	I11_Q20
119	I11_Q19
120	I11_Q18
121	I11_Q17
122	I11_Q16
123	I11_Q15
124	I11_Q14
125	I11_Q13
126	I11_Q12
127	I11_Q11
128	I11_I10
129	I11_I9
130	I11_I8

131	I11_I7
132	I11_I6
133	I11_I5
134	I11_I4
135	I11_I3
136	I11_I2
137	I11_I1
138	I11_0
139	I10_1
140	I10_Q24
141	I10_Q23
142	I10_Q22
143	I10_Q21
144	I10_Q20
145	I10_Q19
146	I10_Q18
147	I10_Q17
148	I10_Q16
149	I10_Q15
150	I10_Q14
151	I10_Q13
152	I10_Q12
153	I10_Q11
154	I10_Q10
155	I10_I9
156	I10_I8
157	I10_I7
158	I10_I6
159	I10_I5
160	I10_I4
161	I10_I3
162	I10_I2

163	I10_I1
164	I10_0
165	I9_1
166	I9_Q24
167	I9_Q23
168	I9_Q22
169	I9_Q21
170	I9_Q20
171	I9_Q19
172	I9_Q18
173	I9_Q17
174	I9_Q16
175	I9_Q15
176	I9_Q14
177	I9_Q13
178	I9_Q12
179	I9_Q11
180	I9_Q10
181	I9_Q9
182	I9_I8
183	I9_I7
184	I9_I6
185	I9_I5
186	I9_I4
187	I9_I3
188	I9_I2
189	I9_I1
190	I9_0
191	I8_1
192	I8_Q24
193	I8_Q23
194	I8_Q22

195	I8_Q21
196	I8_Q20
197	I8_Q19
198	I8_Q18
199	I8_Q17
200	I8_Q16
201	I8_Q15
202	I8_Q14
203	I8_Q13
204	I8_Q12
205	I8_Q11
206	I8_Q10
207	I8_Q9
208	I8_Q8
209	I8_I7
210	I8_I6
211	I8_I5
212	I8_I4
213	I8_I3
214	I8_I2
215	I8_I1
216	I8_0
217	I7_1
218	I7_Q24
219	I7_Q23
220	I7_Q22
221	I7_Q21
222	I7_Q20
223	I7_Q19
224	I7_Q18
225	I7_Q17
226	I7_Q16

227	I7_Q15
228	I7_Q14

229	I7_Q13
230	I7_Q12

231	I7_Q11
-----	--------

Array Index	Correlation
Correlator_Counts_3	
1	I7_Q10
2	I7_Q9
3	I7_Q8
4	I7_Q7
5	I7_I6
6	I7_I5
7	I7_I4
8	I7_I3
9	I7_I2
10	I7_I1
11	I7_0
12	I6_1
13	I6_Q24
14	I6_Q23
15	I6_Q22
16	I6_Q21
17	I6_Q20
18	I6_Q19
19	I6_Q18
20	I6_Q17
21	I6_Q16
22	I6_Q15
23	I6_Q14
24	I6_Q13
25	I6_Q12
26	I6_Q11
27	I6_Q10

28	I6_Q9
29	I6_Q8
30	I6_Q7
31	I6_Q6
32	I6_I5
33	I6_I4
34	I6_I3
35	I6_I2
36	I6_I1
37	I6_0
38	I5_1
39	I5_Q24
40	I5_Q23
41	I5_Q22
42	I5_Q21
43	I5_Q20
44	I5_Q19
45	I5_Q18
46	I5_Q17
47	I5_Q16
48	I5_Q15
49	I5_Q14
50	I5_Q13
51	I5_Q12
52	I5_Q11
53	I5_Q10
54	I5_Q9
55	I5_Q8
56	I5_Q7

57	I5_Q6
58	I5_Q5
59	I5_I4
60	I5_I3
61	I5_I2
62	I5_I1
63	I5_0
64	I4_1
65	I4_Q24
66	I4_Q23
67	I4_Q22
68	I4_Q21
69	I4_Q20
70	I4_Q19
71	I4_Q18
72	I4_Q17
73	I4_Q16
74	I4_Q15
75	I4_Q14
76	I4_Q13
77	I4_Q12
78	I4_Q11
79	I4_Q10
80	I4_Q9
81	I4_Q8
82	I4_Q7
83	I4_Q6
84	I4_Q5
85	I4_Q4

86	I4_I3
87	I4_I2
88	I4_I1
89	I4_0
90	I3_1
91	I3_Q24
92	I3_Q23
93	I3_Q22
94	I3_Q21
95	I3_Q20
96	I3_Q19
97	I3_Q18
98	I3_Q17
99	I3_Q16
100	I3_Q15
101	I3_Q14
102	I3_Q13
103	I3_Q12
104	I3_Q11
105	I3_Q10
106	I3_Q9
107	I3_Q8
108	I3_Q7
109	I3_Q6
110	I3_Q5
111	I3_Q4
112	I3_Q3
113	I3_I2
114	I3_I1
115	I3_0
116	I2_1
117	I2_Q24

118	I2_Q23
119	I2_Q22
120	I2_Q21
121	I2_Q20
122	I2_Q19
123	I2_Q18
124	I2_Q17
125	I2_Q16
126	I2_Q15
127	I2_Q14
128	I2_Q13
129	I2_Q12
130	I2_Q11
131	I2_Q10
132	I2_Q9
133	I2_Q8
134	I2_Q7
135	I2_Q6
136	I2_Q5
137	I2_Q4
138	I2_Q3
139	I2_Q2
140	I2_I1
141	I2_0
142	I1_1
143	I1_Q24
144	I1_Q23
145	I1_Q22
146	I1_Q21
147	I1_Q20
148	I1_Q19
149	I1_Q18

150	I1_Q17
151	I1_Q16
152	I1_Q15
153	I1_Q14
154	I1_Q13
155	I1_Q12
156	I1_Q11
157	I1_Q10
158	I1_Q9
159	I1_Q8
160	I1_Q7
161	I1_Q6
162	I1_Q5
163	I1_Q4
164	I1_Q3
165	I1_Q2
166	I1_Q1
167	I1_0
168	0_1-0
169	0_Q24
170	0_Q23
171	0_Q22
172	0_Q21
173	0_Q20
174	0_Q19
175	0_Q18
176	0_Q17
177	0_Q16
178	0_Q15
179	0_Q14
180	0_Q13
181	0_Q12

182	0_Q11
183	0_Q10
184	0_Q9
185	0_Q8

186	0_Q7
187	0_Q6
188	0_Q5
189	0_Q4

190	0_Q3
191	0_Q2
192	0_Q1
193	0_0-0

Array Index	Correlation
Correlator_Counts_4	
1	1_1-1
2	1_Q48
3	1_Q47
4	1_Q46
5	1_Q45
6	1_Q44
7	1_Q43
8	1_Q42
9	1_Q41
10	1_Q40
11	1_Q39

12	1_Q38
13	1_Q37
14	1_Q36
15	1_Q35
16	1_Q34
17	1_Q33
18	1_Q32
19	1_Q31
20	1_Q30
21	1_Q29
22	1_Q28
23	1_Q27
24	1_Q26

25	1_Q25
26	1_0-1
27	I24_Q48
28	I24_Q47
29	I24_Q46
30	I24_Q45
31	I24_Q44
32	I24_Q43
33	I24_Q42
34	I24_Q41
35	I24_Q40

Array Index	Correlation
Correlator_Counts_5	
1	I24_Q39
2	I24_Q38
3	I24_Q37
4	I24_Q36
5	I24_Q35
6	I24_Q34
7	I24_Q33
8	I24_Q32
9	I24_Q31
10	I24_Q30
11	I24_Q29

12	I24_Q28
13	I24_Q27
14	I24_Q26
15	I24_Q25
16	I23_Q48
17	I23_Q47
18	I23_Q46
19	I23_Q45
20	I23_Q44
21	I23_Q43
22	I23_Q42
23	I23_Q41
24	I23_Q40

25	I23_Q39
26	I23_Q38
27	I23_Q37
28	I23_Q36
29	I23_Q35
30	I23_Q34
31	I23_Q33
32	I23_Q32
33	I23_Q31
34	I23_Q30
35	I23_Q29
36	I23_Q28
37	I23_Q27

38	I23_Q26
39	I23_Q25
40	I22_Q48
41	I22_Q47
42	I22_Q46
43	I22_Q45
44	I22_Q44
45	I22_Q43
46	I22_Q42
47	I22_Q41
48	I22_Q40
49	I22_Q39
50	I22_Q38
51	I22_Q37
52	I22_Q36
53	I22_Q35
54	I22_Q34
55	I22_Q33
56	I22_Q32
57	I22_Q31
58	I22_Q30
59	I22_Q29
60	I22_Q28
61	I22_Q27
62	I22_Q26
63	I22_Q25
64	I21_Q48
65	I21_Q47
66	I21_Q46
67	I21_Q45
68	I21_Q44
69	I21_Q43

70	I21_Q42
71	I21_Q41
72	I21_Q40
73	I21_Q39
74	I21_Q38
75	I21_Q37
76	I21_Q36
77	I21_Q35
78	I21_Q34
79	I21_Q33
80	I21_Q32
81	I21_Q31
82	I21_Q30
83	I21_Q29
84	I21_Q28
85	I21_Q27
86	I21_Q26
87	I21_Q25
88	I20_Q48
89	I20_Q47
90	I20_Q46
91	I20_Q45
92	I20_Q44
93	I20_Q43
94	I20_Q42
95	I20_Q41
96	I20_Q40
97	I20_Q39
98	I20_Q38
99	I20_Q37
100	I20_Q36
101	I20_Q35

102	I20_Q34
103	I20_Q33
104	I20_Q32
105	I20_Q31
106	I20_Q30
107	I20_Q29
108	I20_Q28
109	I20_Q27
110	I20_Q26
111	I20_Q25
112	I19_Q48
113	I19_Q47
114	I19_Q46
115	I19_Q45
116	I19_Q44
117	I19_Q43
118	I19_Q42
119	I19_Q41
120	I19_Q40
121	I19_Q39
122	I19_Q38
123	I19_Q37
124	I19_Q36
125	I19_Q35
126	I19_Q34
127	I19_Q33
128	I19_Q32
129	I19_Q31
130	I19_Q30
131	I19_Q29
132	I19_Q28
133	I19_Q27

134	I19_Q26
135	I19_Q25
136	I18_Q48
137	I18_Q47
138	I18_Q46
139	I18_Q45
140	I18_Q44
141	I18_Q43
142	I18_Q42
143	I18_Q41
144	I18_Q40
145	I18_Q39
146	I18_Q38
147	I18_Q37
148	I18_Q36
149	I18_Q35
150	I18_Q34
151	I18_Q33
152	I18_Q32
153	I18_Q31
154	I18_Q30
155	I18_Q29
156	I18_Q28
157	I18_Q27
158	I18_Q26
159	I18_Q25
160	I17_Q48
161	I17_Q47
162	I17_Q46
163	I17_Q45
164	I17_Q44
165	I17_Q43

166	I17_Q42
167	I17_Q41
168	I17_Q40
169	I17_Q39
170	I17_Q38
171	I17_Q37
172	I17_Q36
173	I17_Q35
174	I17_Q34
175	I17_Q33
176	I17_Q32
177	I17_Q31
178	I17_Q30
179	I17_Q29
180	I17_Q28
181	I17_Q27
182	I17_Q26
183	I17_Q25
184	I16_Q48
185	I16_Q47
186	I16_Q46
187	I16_Q45
188	I16_Q44
189	I16_Q43
190	I16_Q42
191	I16_Q41
192	I16_Q40
193	I16_Q39
194	I16_Q38
195	I16_Q37
196	I16_Q36
197	I16_Q35

198	I16_Q34
199	I16_Q33
200	I16_Q32
201	I16_Q31
202	I16_Q30
203	I16_Q29
204	I16_Q28
205	I16_Q27
206	I16_Q26
207	I16_Q25
208	I15_Q48
209	I15_Q47
210	I15_Q46
211	I15_Q45
212	I15_Q44
213	I15_Q43
214	I15_Q42
215	I15_Q41
216	I15_Q40
217	I15_Q39
218	I15_Q38
219	I15_Q37
220	I15_Q36
221	I15_Q35
222	I15_Q34
223	I15_Q33
224	I15_Q32
225	I15_Q31
226	I15_Q30
227	I15_Q29
228	I15_Q28
229	I15_Q27

230	I15_Q26
231	I15_Q25

Array Index	Correlation
Correlator_Counts_6	
1	I14_Q48
2	I14_Q47
3	I14_Q46
4	I14_Q45
5	I14_Q44
6	I14_Q43
7	I14_Q42
8	I14_Q41
9	I14_Q40
10	I14_Q39
11	I14_Q38
12	I14_Q37
13	I14_Q36
14	I14_Q35
15	I14_Q34
16	I14_Q33
17	I14_Q32
18	I14_Q31
19	I14_Q30
20	I14_Q29
21	I14_Q28
22	I14_Q27
23	I14_Q26
24	I14_Q25
25	I13_Q48
26	I13_Q47
27	I13_Q46

28	I13_Q45
29	I13_Q44
30	I13_Q43
31	I13_Q42
32	I13_Q41
33	I13_Q40
34	I13_Q39
35	I13_Q38
36	I13_Q37
37	I13_Q36
38	I13_Q35
39	I13_Q34
40	I13_Q33
41	I13_Q32
42	I13_Q31
43	I13_Q30
44	I13_Q29
45	I13_Q28
46	I13_Q27
47	I13_Q26
48	I13_Q25
49	I12_Q48
50	I12_Q47
51	I12_Q46
52	I12_Q45
53	I12_Q44
54	I12_Q43
55	I12_Q42
56	I12_Q41

57	I12_Q40
58	I12_Q39
59	I12_Q38
60	I12_Q37
61	I12_Q36
62	I12_Q35
63	I12_Q34
64	I12_Q33
65	I12_Q32
66	I12_Q31
67	I12_Q30
68	I12_Q29
69	I12_Q28
70	I12_Q27
71	I12_Q26
72	I12_Q25
73	I11_Q48
74	I11_Q47
75	I11_Q46
76	I11_Q45
77	I11_Q44
78	I11_Q43
79	I11_Q42
80	I11_Q41
81	I11_Q40
82	I11_Q39
83	I11_Q38
84	I11_Q37
85	I11_Q36

86	I11_Q35
87	I11_Q34
88	I11_Q33
89	I11_Q32
90	I11_Q31
91	I11_Q30
92	I11_Q29
93	I11_Q28
94	I11_Q27
95	I11_Q26
96	I11_Q25
97	I10_Q48
98	I10_Q47
99	I10_Q46
100	I10_Q45
101	I10_Q44
102	I10_Q43
103	I10_Q42
104	I10_Q41
105	I10_Q40
106	I10_Q39
107	I10_Q38
108	I10_Q37
109	I10_Q36
110	I10_Q35
111	I10_Q34
112	I10_Q33
113	I10_Q32
114	I10_Q31
115	I10_Q30
116	I10_Q29
117	I10_Q28

118	I10_Q27
119	I10_Q26
120	I10_Q25
121	I9_Q48
122	I9_Q47
123	I9_Q46
124	I9_Q45
125	I9_Q44
126	I9_Q43
127	I9_Q42
128	I9_Q41
129	I9_Q40
130	I9_Q39
131	I9_Q38
132	I9_Q37
133	I9_Q36
134	I9_Q35
135	I9_Q34
136	I9_Q33
137	I9_Q32
138	I9_Q31
139	I9_Q30
140	I9_Q29
141	I9_Q28
142	I9_Q27
143	I9_Q26
144	I9_Q25
145	I8_Q48
146	I8_Q47
147	I8_Q46
148	I8_Q45
149	I8_Q44

150	I8_Q43
151	I8_Q42
152	I8_Q41
153	I8_Q40
154	I8_Q39
155	I8_Q38
156	I8_Q37
157	I8_Q36
158	I8_Q35
159	I8_Q34
160	I8_Q33
161	I8_Q32
162	I8_Q31
163	I8_Q30
164	I8_Q29
165	I8_Q28
166	I8_Q27
167	I8_Q26
168	I8_Q25
169	I7_Q48
170	I7_Q47
171	I7_Q46
172	I7_Q45
173	I7_Q44
174	I7_Q43
175	I7_Q42
176	I7_Q41
177	I7_Q40
178	I7_Q39
179	I7_Q38
180	I7_Q37
181	I7_Q36

182	I7_Q35
183	I7_Q34
184	I7_Q33
185	I7_Q32
186	I7_Q31
187	I7_Q30
188	I7_Q29
189	I7_Q28
190	I7_Q27
191	I7_Q26
192	I7_Q25
193	I6_Q48
194	I6_Q47
195	I6_Q46
196	I6_Q45
197	I6_Q44
198	I6_Q43

199	I6_Q42
200	I6_Q41
201	I6_Q40
202	I6_Q39
203	I6_Q38
204	I6_Q37
205	I6_Q36
206	I6_Q35
207	I6_Q34
208	I6_Q33
209	I6_Q32
210	I6_Q31
211	I6_Q30
212	I6_Q29
213	I6_Q28
214	I6_Q27
215	I6_Q26

216	I6_Q25
217	I5_Q48
218	I5_Q47
219	I5_Q46
220	I5_Q45
221	I5_Q44
222	I5_Q43
223	I5_Q42
224	I5_Q41
225	I5_Q40
226	I5_Q39
227	I5_Q38
228	I5_Q37
229	I5_Q36
230	I5_Q35
231	I5_Q34

Array Index	Correlation
Correlator_Counts_7	
1	I5_Q33
2	I5_Q32
3	I5_Q31
4	I5_Q30
5	I5_Q29
6	I5_Q28
7	I5_Q27
8	I5_Q26
9	I5_Q25
10	I4_Q48
11	I4_Q47
12	I4_Q46

13	I4_Q45
14	I4_Q44
15	I4_Q43
16	I4_Q42
17	I4_Q41
18	I4_Q40
19	I4_Q39
20	I4_Q38
21	I4_Q37
22	I4_Q36
23	I4_Q35
24	I4_Q34
25	I4_Q33
26	I4_Q32

27	I4_Q31
28	I4_Q30
29	I4_Q29
30	I4_Q28
31	I4_Q27
32	I4_Q26
33	I4_Q25
34	I3_Q48
35	I3_Q47
36	I3_Q46
37	I3_Q45
38	I3_Q44
39	I3_Q43
40	I3_Q42

41	I3_Q41
42	I3_Q40
43	I3_Q39
44	I3_Q38
45	I3_Q37
46	I3_Q36
47	I3_Q35
48	I3_Q34
49	I3_Q33
50	I3_Q32
51	I3_Q31
52	I3_Q30
53	I3_Q29
54	I3_Q28
55	I3_Q27
56	I3_Q26
57	I3_Q25
58	I2_Q48
59	I2_Q47
60	I2_Q46
61	I2_Q45
62	I2_Q44
63	I2_Q43
64	I2_Q42
65	I2_Q41
66	I2_Q40
67	I2_Q39
68	I2_Q38
69	I2_Q37
70	I2_Q36
71	I2_Q35

72	I2_Q34
73	I2_Q33
74	I2_Q32
75	I2_Q31
76	I2_Q30
77	I2_Q29
78	I2_Q28
79	I2_Q27
80	I2_Q26
81	I2_Q25
82	I1_Q48
83	I1_Q47
84	I1_Q46
85	I1_Q45
86	I1_Q44
87	I1_Q43
88	I1_Q42
89	I1_Q41
90	I1_Q40
91	I1_Q39
92	I1_Q38
93	I1_Q37
94	I1_Q36
95	I1_Q35
96	I1_Q34
97	I1_Q33
98	I1_Q32
99	I1_Q31
100	I1_Q30
101	I1_Q29
102	I1_Q28

103	I1_Q27
104	I1_Q26
105	I1_Q25
106	0_1-1
107	0_Q48
108	0_Q47
109	0_Q46
110	0_Q45
111	0_Q44
112	0_Q43
113	0_Q42
114	0_Q41
115	0_Q40
116	0_Q39
117	0_Q38
118	0_Q37
119	0_Q36
120	0_Q35
121	0_Q34
122	0_Q33
123	0_Q32
124	0_Q31
125	0_Q30
126	0_Q29
127	0_Q28
128	0_Q27
129	0_Q26
130	0_Q25
131	0_0-1

Array Index	Correlation
Correlator_Counts_8	
1	1_1-2
2	1_Q72
3	1_Q71
4	1_Q70
5	1_Q69
6	1_Q68
7	1_Q67
8	1_Q66
9	1_Q65
10	1_Q64
11	1_Q63
12	1_Q62
13	1_Q61
14	1_Q60
15	1_Q59
16	1_Q58
17	1_Q57
18	1_Q56
19	1_Q55
20	1_Q54
21	1_Q53
22	1_Q52
23	1_Q51
24	1_Q50
25	1_Q49
26	1_0-2
27	I24_Q72
28	I24_Q71
29	I24_Q70
30	I24_Q69

31	I24_Q68
32	I24_Q67
33	I24_Q66
34	I24_Q65
35	I24_Q64
36	I24_Q63
37	I24_Q62
38	I24_Q61
39	I24_Q60
40	I24_Q59
41	I24_Q58
42	I24_Q57
43	I24_Q56
44	I24_Q55
45	I24_Q54
46	I24_Q53
47	I24_Q52
48	I24_Q51
49	I24_Q50
50	I24_Q49
51	I23_Q72
52	I23_Q71
53	I23_Q70
54	I23_Q69
55	I23_Q68
56	I23_Q67
57	I23_Q66
58	I23_Q65
59	I23_Q64
60	I23_Q63
61	I23_Q62
62	I23_Q61

63	I23_Q60
64	I23_Q59
65	I23_Q58
66	I23_Q57
67	I23_Q56
68	I23_Q55
69	I23_Q54
70	I23_Q53
71	I23_Q52
72	I23_Q51
73	I23_Q50
74	I23_Q49
75	I22_Q72
76	I22_Q71
77	I22_Q70
78	I22_Q69
79	I22_Q68
80	I22_Q67
81	I22_Q66
82	I22_Q65
83	I22_Q64
84	I22_Q63
85	I22_Q62
86	I22_Q61
87	I22_Q60
88	I22_Q59
89	I22_Q58
90	I22_Q57
91	I22_Q56
92	I22_Q55
93	I22_Q54
94	I22_Q53

95	I22_Q52
96	I22_Q51

97	I22_Q50
----	---------

Array Index	Correlation
Correlator_Counts_9	
1	I22_Q49
2	I21_Q72
3	I21_Q71
4	I21_Q70
5	I21_Q69
6	I21_Q68
7	I21_Q67
8	I21_Q66
9	I21_Q65
10	I21_Q64
11	I21_Q63
12	I21_Q62
13	I21_Q61
14	I21_Q60
15	I21_Q59
16	I21_Q58
17	I21_Q57
18	I21_Q56
19	I21_Q55
20	I21_Q54
21	I21_Q53
22	I21_Q52
23	I21_Q51
24	I21_Q50
25	I21_Q49
26	I20_Q72
27	I20_Q71

28	I20_Q70
29	I20_Q69
30	I20_Q68
31	I20_Q67
32	I20_Q66
33	I20_Q65
34	I20_Q64
35	I20_Q63
36	I20_Q62
37	I20_Q61
38	I20_Q60
39	I20_Q59
40	I20_Q58
41	I20_Q57
42	I20_Q56
43	I20_Q55
44	I20_Q54
45	I20_Q53
46	I20_Q52
47	I20_Q51
48	I20_Q50
49	I20_Q49
50	I19_Q72
51	I19_Q71
52	I19_Q70
53	I19_Q69
54	I19_Q68
55	I19_Q67
56	I19_Q66

57	I19_Q65
58	I19_Q64
59	I19_Q63
60	I19_Q62
61	I19_Q61
62	I19_Q60
63	I19_Q59
64	I19_Q58
65	I19_Q57
66	I19_Q56
67	I19_Q55
68	I19_Q54
69	I19_Q53
70	I19_Q52
71	I19_Q51
72	I19_Q50
73	I19_Q49
74	I18_Q72
75	I18_Q71
76	I18_Q70
77	I18_Q69
78	I18_Q68
79	I18_Q67
80	I18_Q66
81	I18_Q65
82	I18_Q64
83	I18_Q63
84	I18_Q62
85	I18_Q61

86	I18_Q60
87	I18_Q59
88	I18_Q58
89	I18_Q57
90	I18_Q56
91	I18_Q55
92	I18_Q54
93	I18_Q53
94	I18_Q52
95	I18_Q51
96	I18_Q50
97	I18_Q49
98	I17_Q72
99	I17_Q71
100	I17_Q70
101	I17_Q69
102	I17_Q68
103	I17_Q67
104	I17_Q66
105	I17_Q65
106	I17_Q64
107	I17_Q63
108	I17_Q62
109	I17_Q61
110	I17_Q60
111	I17_Q59
112	I17_Q58
113	I17_Q57
114	I17_Q56
115	I17_Q55
116	I17_Q54
117	I17_Q53

118	I17_Q52
119	I17_Q51
120	I17_Q50
121	I17_Q49
122	I16_Q72
123	I16_Q71
124	I16_Q70
125	I16_Q69
126	I16_Q68
127	I16_Q67
128	I16_Q66
129	I16_Q65
130	I16_Q64
131	I16_Q63
132	I16_Q62
133	I16_Q61
134	I16_Q60
135	I16_Q59
136	I16_Q58
137	I16_Q57
138	I16_Q56
139	I16_Q55
140	I16_Q54
141	I16_Q53
142	I16_Q52
143	I16_Q51
144	I16_Q50
145	I16_Q49
146	I15_Q72
147	I15_Q71
148	I15_Q70
149	I15_Q69

150	I15_Q68
151	I15_Q67
152	I15_Q66
153	I15_Q65
154	I15_Q64
155	I15_Q63
156	I15_Q62
157	I15_Q61
158	I15_Q60
159	I15_Q59
160	I15_Q58
161	I15_Q57
162	I15_Q56
163	I15_Q55
164	I15_Q54
165	I15_Q53
166	I15_Q52
167	I15_Q51
168	I15_Q50
169	I15_Q49
170	I14_Q72
171	I14_Q71
172	I14_Q70
173	I14_Q69
174	I14_Q68
175	I14_Q67
176	I14_Q66
177	I14_Q65
178	I14_Q64
179	I14_Q63
180	I14_Q62
181	I14_Q61

182	I14_Q60
183	I14_Q59
184	I14_Q58
185	I14_Q57
186	I14_Q56
187	I14_Q55
188	I14_Q54
189	I14_Q53
190	I14_Q52
191	I14_Q51
192	I14_Q50
193	I14_Q49
194	I13_Q72
195	I13_Q71
196	I13_Q70
197	I13_Q69
198	I13_Q68

199	I13_Q67
200	I13_Q66
201	I13_Q65
202	I13_Q64
203	I13_Q63
204	I13_Q62
205	I13_Q61
206	I13_Q60
207	I13_Q59
208	I13_Q58
209	I13_Q57
210	I13_Q56
211	I13_Q55
212	I13_Q54
213	I13_Q53
214	I13_Q52
215	I13_Q51

216	I13_Q50
217	I13_Q49
218	I12_Q72
219	I12_Q71
220	I12_Q70
221	I12_Q69
222	I12_Q68
223	I12_Q67
224	I12_Q66
225	I12_Q65
226	I12_Q64
227	I12_Q63
228	I12_Q62
229	I12_Q61
230	I12_Q60
231	I12_Q59

Array Index	Correlation
Correlator_Counts_10	
1	I12_Q58
2	I12_Q57
3	I12_Q56
4	I12_Q55
5	I12_Q54
6	I12_Q53
7	I12_Q52
8	I12_Q51
9	I12_Q50
10	I12_Q49
11	I11_Q72
12	I11_Q71

13	I11_Q70
14	I11_Q69
15	I11_Q68
16	I11_Q67
17	I11_Q66
18	I11_Q65
19	I11_Q64
20	I11_Q63
21	I11_Q62
22	I11_Q61
23	I11_Q60
24	I11_Q59
25	I11_Q58
26	I11_Q57

27	I11_Q56
28	I11_Q55
29	I11_Q54
30	I11_Q53
31	I11_Q52
32	I11_Q51
33	I11_Q50
34	I11_Q49
35	I10_Q72
36	I10_Q71
37	I10_Q70
38	I10_Q69
39	I10_Q68
40	I10_Q67

41	I10_Q66
42	I10_Q65
43	I10_Q64
44	I10_Q63
45	I10_Q62
46	I10_Q61
47	I10_Q60
48	I10_Q59
49	I10_Q58
50	I10_Q57
51	I10_Q56
52	I10_Q55
53	I10_Q54
54	I10_Q53
55	I10_Q52
56	I10_Q51
57	I10_Q50
58	I10_Q49
59	I9_Q72
60	I9_Q71
61	I9_Q70
62	I9_Q69
63	I9_Q68
64	I9_Q67
65	I9_Q66
66	I9_Q65
67	I9_Q64
68	I9_Q63
69	I9_Q62
70	I9_Q61
71	I9_Q60
72	I9_Q59

73	I9_Q58
74	I9_Q57
75	I9_Q56
76	I9_Q55
77	I9_Q54
78	I9_Q53
79	I9_Q52
80	I9_Q51
81	I9_Q50
82	I9_Q49
83	I8_Q72
84	I8_Q71
85	I8_Q70
86	I8_Q69
87	I8_Q68
88	I8_Q67
89	I8_Q66
90	I8_Q65
91	I8_Q64
92	I8_Q63
93	I8_Q62
94	I8_Q61
95	I8_Q60
96	I8_Q59
97	I8_Q58
98	I8_Q57
99	I8_Q56
100	I8_Q55
101	I8_Q54
102	I8_Q53
103	I8_Q52
104	I8_Q51

105	I8_Q50
106	I8_Q49
107	I7_Q72
108	I7_Q71
109	I7_Q70
110	I7_Q69
111	I7_Q68
112	I7_Q67
113	I7_Q66
114	I7_Q65
115	I7_Q64
116	I7_Q63
117	I7_Q62
118	I7_Q61
119	I7_Q60
120	I7_Q59
121	I7_Q58
122	I7_Q57
123	I7_Q56
124	I7_Q55
125	I7_Q54
126	I7_Q53
127	I7_Q52
128	I7_Q51
129	I7_Q50
130	I7_Q49
131	I6_Q72
132	I6_Q71
133	I6_Q70
134	I6_Q69
135	I6_Q68
136	I6_Q67

137	I6_Q66
138	I6_Q65
139	I6_Q64
140	I6_Q63
141	I6_Q62
142	I6_Q61
143	I6_Q60
144	I6_Q59
145	I6_Q58
146	I6_Q57
147	I6_Q56
148	I6_Q55
149	I6_Q54
150	I6_Q53
151	I6_Q52
152	I6_Q51
153	I6_Q50
154	I6_Q49
155	I5_Q72
156	I5_Q71
157	I5_Q70
158	I5_Q69
159	I5_Q68
160	I5_Q67
161	I5_Q66
162	I5_Q65
163	I5_Q64
164	I5_Q63
165	I5_Q62
166	I5_Q61
167	I5_Q60
168	I5_Q59

169	I5_Q58
170	I5_Q57
171	I5_Q56
172	I5_Q55
173	I5_Q54
174	I5_Q53
175	I5_Q52
176	I5_Q51
177	I5_Q50
178	I5_Q49
179	I4_Q72
180	I4_Q71
181	I4_Q70
182	I4_Q69
183	I4_Q68
184	I4_Q67
185	I4_Q66
186	I4_Q65
187	I4_Q64
188	I4_Q63
189	I4_Q62
190	I4_Q61
191	I4_Q60
192	I4_Q59
193	I4_Q58
194	I4_Q57
195	I4_Q56
196	I4_Q55
197	I4_Q54
198	I4_Q53
199	I4_Q52
200	I4_Q51

201	I4_Q50
202	I4_Q49
203	I3_Q72
204	I3_Q71
205	I3_Q70
206	I3_Q69
207	I3_Q68
208	I3_Q67
209	I3_Q66
210	I3_Q65
211	I3_Q64
212	I3_Q63
213	I3_Q62
214	I3_Q61
215	I3_Q60
216	I3_Q59
217	I3_Q58
218	I3_Q57
219	I3_Q56
220	I3_Q55
221	I3_Q54
222	I3_Q53
223	I3_Q52
224	I3_Q51
225	I3_Q50
226	I3_Q49
227	I2_Q72
228	I2_Q71
229	I2_Q70
230	I2_Q69
231	I2_Q68

Array Index	Correlation
Correlator_Counts_11	
1	I2_Q67
2	I2_Q66
3	I2_Q65
4	I2_Q64
5	I2_Q63
6	I2_Q62
7	I2_Q61
8	I2_Q60
9	I2_Q59
10	I2_Q58
11	I2_Q57
12	I2_Q56
13	I2_Q55
14	I2_Q54
15	I2_Q53
16	I2_Q52
17	I2_Q51
18	I2_Q50
19	I2_Q49
20	I1_Q72
21	I1_Q71
22	I1_Q70

23	I1_Q69
24	I1_Q68
25	I1_Q67
26	I1_Q66
27	I1_Q65
28	I1_Q64
29	I1_Q63
30	I1_Q62
31	I1_Q61
32	I1_Q60
33	I1_Q59
34	I1_Q58
35	I1_Q57
36	I1_Q56
37	I1_Q55
38	I1_Q54
39	I1_Q53
40	I1_Q52
41	I1_Q51
42	I1_Q50
43	I1_Q49
44	0_1-2
45	0_Q72
46	0_Q71

47	0_Q70
48	0_Q69
49	0_Q68
50	0_Q67
51	0_Q66
52	0_Q65
53	0_Q64
54	0_Q63
55	0_Q62
56	0_Q61
57	0_Q60
58	0_Q59
59	0_Q58
60	0_Q57
61	0_Q56
62	0_Q55
63	0_Q54
64	0_Q53
65	0_Q52
66	0_Q51
67	0_Q50
68	0_Q49
69	0_0-2

Array Index	Correlation
Correlator_Counts_12	
1	1_1-3
2	1_0-3
3	I48_1
4	I48_I24
5	I48_I23

6	I48_I22
7	I48_I21
8	I48_I20
9	I48_I19
10	I48_I18
11	I48_I17
12	I48_I16

13	I48_I15
14	I48_I14
15	I48_I13
16	I48_I12
17	I48_I11
18	I48_I10
19	I48_I9

20	I48_I8
21	I48_I7
22	I48_I6
23	I48_I5
24	I48_I4
25	I48_I3
26	I48_I2
27	I48_I1
28	I48_0
29	I47_1
30	I47_I24
31	I47_I23
32	I47_I22
33	I47_I21
34	I47_I20
35	I47_I19
36	I47_I18
37	I47_I17
38	I47_I16
39	I47_I15
40	I47_I14
41	I47_I13
42	I47_I12
43	I47_I11
44	I47_I10
45	I47_I9
46	I47_I8
47	I47_I7
48	I47_I6
49	I47_I5
50	I47_I4
51	I47_I3

52	I47_I2
53	I47_I1
54	I47_0
55	I46_1
56	I46_I24
57	I46_I23
58	I46_I22
59	I46_I21
60	I46_I20
61	I46_I19
62	I46_I18
63	I46_I17
64	I46_I16
65	I46_I15
66	I46_I14
67	I46_I13
68	I46_I12
69	I46_I11
70	I46_I10
71	I46_I9
72	I46_I8
73	I46_I7
74	I46_I6
75	I46_I5
76	I46_I4
77	I46_I3
78	I46_I2
79	I46_I1
80	I46_0
81	I45_1
82	I45_I24
83	I45_I23

84	I45_I22
85	I45_I21
86	I45_I20
87	I45_I19
88	I45_I18
89	I45_I17
90	I45_I16
91	I45_I15
92	I45_I14
93	I45_I13
94	I45_I12
95	I45_I11
96	I45_I10
97	I45_I9
98	I45_I8
99	I45_I7
100	I45_I6
101	I45_I5
102	I45_I4
103	I45_I3
104	I45_I2
105	I45_I1
106	I45_0
107	I44_1
108	I44_I24
109	I44_I23
110	I44_I22
111	I44_I21
112	I44_I20
113	I44_I19
114	I44_I18
115	I44_I17

116	I44_I16
117	I44_I15
118	I44_I14
119	I44_I13
120	I44_I12
121	I44_I11
122	I44_I10
123	I44_I9
124	I44_I8
125	I44_I7
126	I44_I6
127	I44_I5
128	I44_I4
129	I44_I3
130	I44_I2

131	I44_I1
132	I44_0
133	I43_1
134	I43_I24
135	I43_I23
136	I43_I22
137	I43_I21
138	I43_I20
139	I43_I19
140	I43_I18
141	I43_I17
142	I43_I16
143	I43_I15
144	I43_I14
145	I43_I13

146	I43_I12
147	I43_I11
148	I43_I10
149	I43_I9
150	I43_I8
151	I43_I7
152	I43_I6
153	I43_I5
154	I43_I4
155	I43_I3
156	I43_I2
157	I43_I1
158	I43_0
159	I42_1

Array Index	Correlation
Correlator_Counts_13	
1	I42_I24
2	I42_I23
3	I42_I22
4	I42_I21
5	I42_I20
6	I42_I19
7	I42_I18
8	I42_I17
9	I42_I16
10	I42_I15
11	I42_I14
12	I42_I13
13	I42_I12
14	I42_I11

15	I42_I10
16	I42_I9
17	I42_I8
18	I42_I7
19	I42_I6
20	I42_I5
21	I42_I4
22	I42_I3
23	I42_I2
24	I42_I1
25	I42_0
26	I41_1
27	I41_I24
28	I41_I23
29	I41_I22
30	I41_I21

31	I41_I20
32	I41_I19
33	I41_I18
34	I41_I17
35	I41_I16
36	I41_I15
37	I41_I14
38	I41_I13
39	I41_I12
40	I41_I11
41	I41_I10
42	I41_I9
43	I41_I8
44	I41_I7
45	I41_I6
46	I41_I5

47	I41_I4
48	I41_I3
49	I41_I2
50	I41_I1
51	I41_0
52	I40_1
53	I40_I24
54	I40_I23
55	I40_I22
56	I40_I21
57	I40_I20
58	I40_I19
59	I40_I18
60	I40_I17
61	I40_I16
62	I40_I15
63	I40_I14
64	I40_I13
65	I40_I12
66	I40_I11
67	I40_I10
68	I40_I9
69	I40_I8
70	I40_I7
71	I40_I6
72	I40_I5
73	I40_I4
74	I40_I3
75	I40_I2
76	I40_I1
77	I40_0
78	I39_1

79	I39_I24
80	I39_I23
81	I39_I22
82	I39_I21
83	I39_I20
84	I39_I19
85	I39_I18
86	I39_I17
87	I39_I16
88	I39_I15
89	I39_I14
90	I39_I13
91	I39_I12
92	I39_I11
93	I39_I10
94	I39_I9
95	I39_I8
96	I39_I7
97	I39_I6
98	I39_I5
99	I39_I4
100	I39_I3
101	I39_I2
102	I39_I1
103	I39_0
104	I38_1
105	I38_I24
106	I38_I23
107	I38_I22
108	I38_I21
109	I38_I20
110	I38_I19

111	I38_I18
112	I38_I17
113	I38_I16
114	I38_I15
115	I38_I14
116	I38_I13
117	I38_I12
118	I38_I11
119	I38_I10
120	I38_I9
121	I38_I8
122	I38_I7
123	I38_I6
124	I38_I5
125	I38_I4
126	I38_I3
127	I38_I2
128	I38_I1
129	I38_0
130	I37_1
131	I37_I24
132	I37_I23
133	I37_I22
134	I37_I21
135	I37_I20
136	I37_I19
137	I37_I18
138	I37_I17
139	I37_I16
140	I37_I15
141	I37_I14
142	I37_I13

143	I37_I12
144	I37_I11
145	I37_I10
146	I37_I9
147	I37_I8
148	I37_I7
149	I37_I6
150	I37_I5
151	I37_I4
152	I37_I3
153	I37_I2
154	I37_I1
155	I37_0
156	I36_1
157	I36_I24
158	I36_I23
159	I36_I22
160	I36_I21
161	I36_I20
162	I36_I19
163	I36_I18
164	I36_I17
165	I36_I16
166	I36_I15
167	I36_I14
168	I36_I13
169	I36_I12
170	I36_I11
171	I36_I10
172	I36_I9

173	I36_I8
174	I36_I7
175	I36_I6
176	I36_I5
177	I36_I4
178	I36_I3
179	I36_I2
180	I36_I1
181	I36_0
182	I35_1
183	I35_I24
184	I35_I23
185	I35_I22
186	I35_I21
187	I35_I20
188	I35_I19
189	I35_I18
190	I35_I17
191	I35_I16
192	I35_I15
193	I35_I14
194	I35_I13
195	I35_I12
196	I35_I11
197	I35_I10
198	I35_I9
199	I35_I8
200	I35_I7
201	I35_I6
202	I35_I5

203	I35_I4
204	I35_I3
205	I35_I2
206	I35_I1
207	I35_0
208	I34_1
209	I34_I24
210	I34_I23
211	I34_I22
212	I34_I21
213	I34_I20
214	I34_I19
215	I34_I18
216	I34_I17
217	I34_I16
218	I34_I15
219	I34_I14
220	I34_I13
221	I34_I12
222	I34_I11
223	I34_I10
224	I34_I9
225	I34_I8
226	I34_I7
227	I34_I6
228	I34_I5
229	I34_I4
230	I34_I3
231	I34_I2

Array Index	Correlation
Correlator_Counts_14	
1	I34_I1
2	I34_0
3	I33_1
4	I33_I24
5	I33_I23
6	I33_I22
7	I33_I21
8	I33_I20
9	I33_I19
10	I33_I18
11	I33_I17
12	I33_I16
13	I33_I15
14	I33_I14
15	I33_I13
16	I33_I12
17	I33_I11
18	I33_I10
19	I33_I9
20	I33_I8
21	I33_I7
22	I33_I6
23	I33_I5
24	I33_I4
25	I33_I3
26	I33_I2
27	I33_I1
28	I33_0
29	I32_1
30	I32_I24

31	I32_I23
32	I32_I22
33	I32_I21
34	I32_I20
35	I32_I19
36	I32_I18
37	I32_I17
38	I32_I16
39	I32_I15
40	I32_I14
41	I32_I13
42	I32_I12
43	I32_I11
44	I32_I10
45	I32_I9
46	I32_I8
47	I32_I7
48	I32_I6
49	I32_I5
50	I32_I4
51	I32_I3
52	I32_I2
53	I32_I1
54	I32_0
55	I31_1
56	I31_I24
57	I31_I23
58	I31_I22
59	I31_I21
60	I31_I20
61	I31_I19
62	I31_I18

63	I31_I17
64	I31_I16
65	I31_I15
66	I31_I14
67	I31_I13
68	I31_I12
69	I31_I11
70	I31_I10
71	I31_I9
72	I31_I8
73	I31_I7
74	I31_I6
75	I31_I5
76	I31_I4
77	I31_I3
78	I31_I2
79	I31_I1
80	I31_0
81	I30_1
82	I30_I24
83	I30_I23
84	I30_I22
85	I30_I21
86	I30_I20
87	I30_I19
88	I30_I18
89	I30_I17
90	I30_I16
91	I30_I15
92	I30_I14
93	I30_I13
94	I30_I12

95	I30_I11
96	I30_I10
97	I30_I9
98	I30_I8
99	I30_I7
100	I30_I6
101	I30_I5
102	I30_I4
103	I30_I3
104	I30_I2
105	I30_I1
106	I30_0
107	I29_1
108	I29_I24
109	I29_I23
110	I29_I22
111	I29_I21
112	I29_I20
113	I29_I19
114	I29_I18
115	I29_I17
116	I29_I16
117	I29_I15
118	I29_I14
119	I29_I13
120	I29_I12
121	I29_I11
122	I29_I10
123	I29_I9
124	I29_I8
125	I29_I7
126	I29_I6

127	I29_I5
128	I29_I4
129	I29_I3
130	I29_I2
131	I29_I1
132	I29_0
133	I28_1
134	I28_I24
135	I28_I23
136	I28_I22
137	I28_I21
138	I28_I20
139	I28_I19
140	I28_I18
141	I28_I17
142	I28_I16
143	I28_I15
144	I28_I14
145	I28_I13
146	I28_I12
147	I28_I11
148	I28_I10
149	I28_I9
150	I28_I8
151	I28_I7
152	I28_I6
153	I28_I5
154	I28_I4
155	I28_I3
156	I28_I2
157	I28_I1
158	I28_0

159	I27_1
160	I27_I24
161	I27_I23
162	I27_I22
163	I27_I21
164	I27_I20
165	I27_I19
166	I27_I18
167	I27_I17
168	I27_I16
169	I27_I15
170	I27_I14
171	I27_I13
172	I27_I12
173	I27_I11
174	I27_I10
175	I27_I9
176	I27_I8
177	I27_I7
178	I27_I6
179	I27_I5
180	I27_I4
181	I27_I3
182	I27_I2
183	I27_I1
184	I27_0
185	I26_1
186	I26_I24
187	I26_I23
188	I26_I22
189	I26_I21
190	I26_I20

191	I26_I19
192	I26_I18
193	I26_I17
194	I26_I16
195	I26_I15
196	I26_I14
197	I26_I13
198	I26_I12
199	I26_I11
200	I26_I10
201	I26_I9
202	I26_I8
203	I26_I7
204	I26_I6
205	I26_I5

206	I26_I4
207	I26_I3
208	I26_I2
209	I26_I1
210	I26_0
211	I25_1
212	I25_I24
213	I25_I23
214	I25_I22
215	I25_I21
216	I25_I20
217	I25_I19
218	I25_I18
219	I25_I17
220	I25_I16

221	I25_I15
222	I25_I14
223	I25_I13
224	I25_I12
225	I25_I11
226	I25_I10
227	I25_I9
228	I25_I8
229	I25_I7
230	I25_I6
231	I25_I5

Array Index	Correlation
Correlator_Counts_15	
1	I25_I4
2	I25_I3
3	I25_I2
4	I25_I1
5	I25_0
6	0_1-3
7	0_0-3

Array Index	Correlation
Correlator_Counts_16	
1	1_1-4
2	1_0-4
3	I48_Q48
4	I48_I47

5	I48_I46
6	I48_I45
7	I48_I44
8	I48_I43
9	I48_I42
10	I48_I41

11	I48_I40
12	I48_I39
13	I48_I38
14	I48_I37
15	I48_I36
16	I48_I35

17	I48_I34
18	I48_I33
19	I48_I32
20	I48_I31
21	I48_I30
22	I48_I29
23	I48_I28
24	I48_I27
25	I48_I26
26	I48_I25
27	I47_Q48
28	I47_Q47
29	I47_I46
30	I47_I45
31	I47_I44
32	I47_I43
33	I47_I42
34	I47_I41
35	I47_I40
36	I47_I39
37	I47_I38
38	I47_I37
39	I47_I36
40	I47_I35
41	I47_I34
42	I47_I33
43	I47_I32
44	I47_I31
45	I47_I30
46	I47_I29
47	I47_I28
48	I47_I27

49	I47_I26
50	I47_I25
51	I46_Q48
52	I46_Q47
53	I46_Q46
54	I46_I45
55	I46_I44
56	I46_I43
57	I46_I42
58	I46_I41
59	I46_I40
60	I46_I39
61	I46_I38
62	I46_I37
63	I46_I36
64	I46_I35
65	I46_I34
66	I46_I33
67	I46_I32
68	I46_I31
69	I46_I30
70	I46_I29
71	I46_I28
72	I46_I27
73	I46_I26
74	I46_I25
75	I45_Q48
76	I45_Q47
77	I45_Q46
78	I45_Q45
79	I45_I44
80	I45_I43

81	I45_I42
82	I45_I41
83	I45_I40
84	I45_I39
85	I45_I38
86	I45_I37
87	I45_I36
88	I45_I35
89	I45_I34
90	I45_I33
91	I45_I32
92	I45_I31
93	I45_I30
94	I45_I29
95	I45_I28
96	I45_I27
97	I45_I26
98	I45_I25
99	I44_Q48
100	I44_Q47
101	I44_Q46
102	I44_Q45
103	I44_Q44
104	I44_I43
105	I44_I42
106	I44_I41
107	I44_I40
108	I44_I39
109	I44_I38
110	I44_I37
111	I44_I36
112	I44_I35

113	I44_I34
114	I44_I33
115	I44_I32
116	I44_I31
117	I44_I30
118	I44_I29
119	I44_I28
120	I44_I27
121	I44_I26
122	I44_I25
123	I43_Q48
124	I43_Q47
125	I43_Q46
126	I43_Q45
127	I43_Q44
128	I43_Q43
129	I43_I42
130	I43_I41
131	I43_I40
132	I43_I39
133	I43_I38
134	I43_I37
135	I43_I36
136	I43_I35
137	I43_I34
138	I43_I33
139	I43_I32
140	I43_I31
141	I43_I30
142	I43_I29
143	I43_I28
144	I43_I27

145	I43_I26
146	I43_I25
147	I42_Q48
148	I42_Q47
149	I42_Q46
150	I42_Q45
151	I42_Q44
152	I42_Q43
153	I42_Q42
154	I42_I41
155	I42_I40
156	I42_I39
157	I42_I38
158	I42_I37
159	I42_I36
160	I42_I35
161	I42_I34
162	I42_I33
163	I42_I32
164	I42_I31
165	I42_I30
166	I42_I29
167	I42_I28
168	I42_I27
169	I42_I26
170	I42_I25
171	I41_Q48
172	I41_Q47
173	I41_Q46
174	I41_Q45
175	I41_Q44
176	I41_Q43

177	I41_Q42
178	I41_Q41
179	I41_I40
180	I41_I39
181	I41_I38
182	I41_I37
183	I41_I36
184	I41_I35
185	I41_I34
186	I41_I33
187	I41_I32
188	I41_I31
189	I41_I30
190	I41_I29
191	I41_I28
192	I41_I27
193	I41_I26
194	I41_I25
195	I40_Q48
196	I40_Q47
197	I40_Q46
198	I40_Q45
199	I40_Q44
200	I40_Q43
201	I40_Q42
202	I40_Q41
203	I40_Q40
204	I40_I39
205	I40_I38
206	I40_I37
207	I40_I36
208	I40_I35

209	I40_I34
210	I40_I33
211	I40_I32
212	I40_I31
213	I40_I30

214	I40_I29
215	I40_I28
216	I40_I27
217	I40_I26
218	I40_I25

219	I39_Q48
220	I39_Q47
221	I39_Q46

Array Index	Correlation
Correlator_Counts_17	
1	I39_Q45
2	I39_Q44
3	I39_Q43
4	I39_Q42
5	I39_Q41
6	I39_Q40
7	I39_Q39
8	I39_I38
9	I39_I37
10	I39_I36
11	I39_I35
12	I39_I34
13	I39_I33
14	I39_I32
15	I39_I31
16	I39_I30
17	I39_I29
18	I39_I28
19	I39_I27
20	I39_I26
21	I39_I25
22	I38_Q48
23	I38_Q47
24	I38_Q46

25	I38_Q45
26	I38_Q44
27	I38_Q43
28	I38_Q42
29	I38_Q41
30	I38_Q40
31	I38_Q39
32	I38_Q38
33	I38_I37
34	I38_I36
35	I38_I35
36	I38_I34
37	I38_I33
38	I38_I32
39	I38_I31
40	I38_I30
41	I38_I29
42	I38_I28
43	I38_I27
44	I38_I26
45	I38_I25
46	I37_Q48
47	I37_Q47
48	I37_Q46
49	I37_Q45
50	I37_Q44

51	I37_Q43
52	I37_Q42
53	I37_Q41
54	I37_Q40
55	I37_Q39
56	I37_Q38
57	I37_Q37
58	I37_I36
59	I37_I35
60	I37_I34
61	I37_I33
62	I37_I32
63	I37_I31
64	I37_I30
65	I37_I29
66	I37_I28
67	I37_I27
68	I37_I26
69	I37_I25
70	I36_Q48
71	I36_Q47
72	I36_Q46
73	I36_Q45
74	I36_Q44
75	I36_Q43
76	I36_Q42

77	I36_Q41
78	I36_Q40
79	I36_Q39
80	I36_Q38
81	I36_Q37
82	I36_Q36
83	I36_I35
84	I36_I34
85	I36_I33
86	I36_I32
87	I36_I31
88	I36_I30
89	I36_I29
90	I36_I28
91	I36_I27
92	I36_I26
93	I36_I25
94	I35_Q48
95	I35_Q47
96	I35_Q46
97	I35_Q45
98	I35_Q44
99	I35_Q43
100	I35_Q42
101	I35_Q41
102	I35_Q40
103	I35_Q39
104	I35_Q38
105	I35_Q37
106	I35_Q36
107	I35_Q35
108	I35_I34

109	I35_I33
110	I35_I32
111	I35_I31
112	I35_I30
113	I35_I29
114	I35_I28
115	I35_I27
116	I35_I26
117	I35_I25
118	I34_Q48
119	I34_Q47
120	I34_Q46
121	I34_Q45
122	I34_Q44
123	I34_Q43
124	I34_Q42
125	I34_Q41
126	I34_Q40
127	I34_Q39
128	I34_Q38
129	I34_Q37
130	I34_Q36
131	I34_Q35
132	I34_Q34
133	I34_I33
134	I34_I32
135	I34_I31
136	I34_I30
137	I34_I29
138	I34_I28
139	I34_I27
140	I34_I26

141	I34_I25
142	I33_Q48
143	I33_Q47
144	I33_Q46
145	I33_Q45
146	I33_Q44
147	I33_Q43
148	I33_Q42
149	I33_Q41
150	I33_Q40
151	I33_Q39
152	I33_Q38
153	I33_Q37
154	I33_Q36
155	I33_Q35
156	I33_Q34
157	I33_Q33
158	I33_I32
159	I33_I31
160	I33_I30
161	I33_I29
162	I33_I28
163	I33_I27
164	I33_I26
165	I33_I25
166	I32_Q48
167	I32_Q47
168	I32_Q46
169	I32_Q45
170	I32_Q44
171	I32_Q43
172	I32_Q42

173	I32_Q41
174	I32_Q40
175	I32_Q39
176	I32_Q38
177	I32_Q37
178	I32_Q36
179	I32_Q35
180	I32_Q34
181	I32_Q33
182	I32_Q32
183	I32_I31
184	I32_I30
185	I32_I29
186	I32_I28
187	I32_I27
188	I32_I26
189	I32_I25
190	I31_Q48
191	I31_Q47
192	I31_Q46

193	I31_Q45
194	I31_Q44
195	I31_Q43
196	I31_Q42
197	I31_Q41
198	I31_Q40
199	I31_Q39
200	I31_Q38
201	I31_Q37
202	I31_Q36
203	I31_Q35
204	I31_Q34
205	I31_Q33
206	I31_Q32
207	I31_Q31
208	I31_I30
209	I31_I29
210	I31_I28
211	I31_I27
212	I31_I26

213	I31_I25
214	I30_Q48
215	I30_Q47
216	I30_Q46
217	I30_Q45
218	I30_Q44
219	I30_Q43
220	I30_Q42
221	I30_Q41
222	I30_Q40
223	I30_Q39
224	I30_Q38
225	I30_Q37
226	I30_Q36
227	I30_Q35
228	I30_Q34
229	I30_Q33
230	I30_Q32
231	I30_Q31

Array Index	Correlation
Correlator_Counts_18	
1	I30_Q30
2	I30_I29
3	I30_I28
4	I30_I27
5	I30_I26
6	I30_I25
7	I29_Q48
8	I29_Q47
9	I29_Q46

10	I29_Q45
11	I29_Q44
12	I29_Q43
13	I29_Q42
14	I29_Q41
15	I29_Q40
16	I29_Q39
17	I29_Q38
18	I29_Q37
19	I29_Q36
20	I29_Q35

21	I29_Q34
22	I29_Q33
23	I29_Q32
24	I29_Q31
25	I29_Q30
26	I29_Q29
27	I29_I28
28	I29_I27
29	I29_I26
30	I29_I25
31	I28_Q48

32	I28_Q47
33	I28_Q46
34	I28_Q45
35	I28_Q44
36	I28_Q43
37	I28_Q42
38	I28_Q41
39	I28_Q40
40	I28_Q39
41	I28_Q38
42	I28_Q37
43	I28_Q36
44	I28_Q35
45	I28_Q34
46	I28_Q33
47	I28_Q32
48	I28_Q31
49	I28_Q30
50	I28_Q29
51	I28_Q28
52	I28_I27
53	I28_I26
54	I28_I25
55	I27_Q48
56	I27_Q47
57	I27_Q46
58	I27_Q45
59	I27_Q44
60	I27_Q43
61	I27_Q42
62	I27_Q41
63	I27_Q40

64	I27_Q39
65	I27_Q38
66	I27_Q37
67	I27_Q36
68	I27_Q35
69	I27_Q34
70	I27_Q33
71	I27_Q32
72	I27_Q31
73	I27_Q30
74	I27_Q29
75	I27_Q28
76	I27_Q27
77	I27_I26
78	I27_I25
79	I26_Q48
80	I26_Q47
81	I26_Q46
82	I26_Q45
83	I26_Q44
84	I26_Q43
85	I26_Q42
86	I26_Q41
87	I26_Q40
88	I26_Q39
89	I26_Q38
90	I26_Q37
91	I26_Q36
92	I26_Q35
93	I26_Q34
94	I26_Q33
95	I26_Q32

96	I26_Q31
97	I26_Q30
98	I26_Q29
99	I26_Q28
100	I26_Q27
101	I26_Q26
102	I26_I25
103	I25_Q48
104	I25_Q47
105	I25_Q46
106	I25_Q45
107	I25_Q44
108	I25_Q43
109	I25_Q42
110	I25_Q41
111	I25_Q40
112	I25_Q39
113	I25_Q38
114	I25_Q37
115	I25_Q36
116	I25_Q35
117	I25_Q34
118	I25_Q33
119	I25_Q32
120	I25_Q31
121	I25_Q30
122	I25_Q29
123	I25_Q28
124	I25_Q27
125	I25_Q26
126	I25_Q25
127	0_1-4

128	0_0-4
-----	-------

Array Index	Correlation
Correlator_Counts_19	
1	1_1-5
2	1_0-5
3	I48_Q72
4	I48_Q71
5	I48_Q70
6	I48_Q69
7	I48_Q68
8	I48_Q67
9	I48_Q66
10	I48_Q65
11	I48_Q64
12	I48_Q63
13	I48_Q62
14	I48_Q61
15	I48_Q60
16	I48_Q59
17	I48_Q58
18	I48_Q57
19	I48_Q56
20	I48_Q55
21	I48_Q54
22	I48_Q53
23	I48_Q52
24	I48_Q51
25	I48_Q50
26	I48_Q49
27	I47_Q72
28	I47_Q71

29	I47_Q70
30	I47_Q69
31	I47_Q68
32	I47_Q67
33	I47_Q66
34	I47_Q65
35	I47_Q64
36	I47_Q63
37	I47_Q62
38	I47_Q61
39	I47_Q60
40	I47_Q59
41	I47_Q58
42	I47_Q57
43	I47_Q56
44	I47_Q55
45	I47_Q54
46	I47_Q53
47	I47_Q52
48	I47_Q51
49	I47_Q50
50	I47_Q49
51	I46_Q72
52	I46_Q71
53	I46_Q70
54	I46_Q69
55	I46_Q68
56	I46_Q67
57	I46_Q66
58	I46_Q65

59	I46_Q64
60	I46_Q63
61	I46_Q62
62	I46_Q61
63	I46_Q60
64	I46_Q59
65	I46_Q58
66	I46_Q57
67	I46_Q56
68	I46_Q55
69	I46_Q54
70	I46_Q53
71	I46_Q52
72	I46_Q51
73	I46_Q50
74	I46_Q49
75	I45_Q72
76	I45_Q71
77	I45_Q70
78	I45_Q69
79	I45_Q68
80	I45_Q67
81	I45_Q66
82	I45_Q65
83	I45_Q64
84	I45_Q63
85	I45_Q62
86	I45_Q61
87	I45_Q60
88	I45_Q59

89	I45_Q58
90	I45_Q57
91	I45_Q56
92	I45_Q55

93	I45_Q54
94	I45_Q53
95	I45_Q52
96	I45_Q51

97	I45_Q50
98	I45_Q49
99	I44_Q72
100	I44_Q71

Array Index	Correlation
Correlator_Counts_20	
1	I44_Q70
2	I44_Q69
3	I44_Q68
4	I44_Q67
5	I44_Q66
6	I44_Q65
7	I44_Q64
8	I44_Q63
9	I44_Q62
10	I44_Q61
11	I44_Q60
12	I44_Q59
13	I44_Q58
14	I44_Q57
15	I44_Q56
16	I44_Q55
17	I44_Q54
18	I44_Q53
19	I44_Q52
20	I44_Q51
21	I44_Q50
22	I44_Q49
23	I43_Q72
24	I43_Q71
25	I43_Q70

26	I43_Q69
27	I43_Q68
28	I43_Q67
29	I43_Q66
30	I43_Q65
31	I43_Q64
32	I43_Q63
33	I43_Q62
34	I43_Q61
35	I43_Q60
36	I43_Q59
37	I43_Q58
38	I43_Q57
39	I43_Q56
40	I43_Q55
41	I43_Q54
42	I43_Q53
43	I43_Q52
44	I43_Q51
45	I43_Q50
46	I43_Q49
47	I42_Q72
48	I42_Q71
49	I42_Q70
50	I42_Q69
51	I42_Q68
52	I42_Q67

53	I42_Q66
54	I42_Q65
55	I42_Q64
56	I42_Q63
57	I42_Q62
58	I42_Q61
59	I42_Q60
60	I42_Q59
61	I42_Q58
62	I42_Q57
63	I42_Q56
64	I42_Q55
65	I42_Q54
66	I42_Q53
67	I42_Q52
68	I42_Q51
69	I42_Q50
70	I42_Q49
71	I41_Q72
72	I41_Q71
73	I41_Q70
74	I41_Q69
75	I41_Q68
76	I41_Q67
77	I41_Q66
78	I41_Q65
79	I41_Q64

80	I41_Q63
81	I41_Q62
82	I41_Q61
83	I41_Q60
84	I41_Q59
85	I41_Q58
86	I41_Q57
87	I41_Q56
88	I41_Q55
89	I41_Q54
90	I41_Q53
91	I41_Q52
92	I41_Q51
93	I41_Q50
94	I41_Q49
95	I40_Q72
96	I40_Q71
97	I40_Q70
98	I40_Q69
99	I40_Q68
100	I40_Q67
101	I40_Q66
102	I40_Q65
103	I40_Q64
104	I40_Q63
105	I40_Q62
106	I40_Q61
107	I40_Q60
108	I40_Q59
109	I40_Q58
110	I40_Q57
111	I40_Q56

112	I40_Q55
113	I40_Q54
114	I40_Q53
115	I40_Q52
116	I40_Q51
117	I40_Q50
118	I40_Q49
119	I39_Q72
120	I39_Q71
121	I39_Q70
122	I39_Q69
123	I39_Q68
124	I39_Q67
125	I39_Q66
126	I39_Q65
127	I39_Q64
128	I39_Q63
129	I39_Q62
130	I39_Q61
131	I39_Q60
132	I39_Q59
133	I39_Q58
134	I39_Q57
135	I39_Q56
136	I39_Q55
137	I39_Q54
138	I39_Q53
139	I39_Q52
140	I39_Q51
141	I39_Q50
142	I39_Q49
143	I38_Q72

144	I38_Q71
145	I38_Q70
146	I38_Q69
147	I38_Q68
148	I38_Q67
149	I38_Q66
150	I38_Q65
151	I38_Q64
152	I38_Q63
153	I38_Q62
154	I38_Q61
155	I38_Q60
156	I38_Q59
157	I38_Q58
158	I38_Q57
159	I38_Q56
160	I38_Q55
161	I38_Q54
162	I38_Q53
163	I38_Q52
164	I38_Q51
165	I38_Q50
166	I38_Q49
167	I37_Q72
168	I37_Q71
169	I37_Q70
170	I37_Q69
171	I37_Q68
172	I37_Q67
173	I37_Q66
174	I37_Q65
175	I37_Q64

176	I37_Q63
177	I37_Q62
178	I37_Q61
179	I37_Q60
180	I37_Q59
181	I37_Q58
182	I37_Q57
183	I37_Q56
184	I37_Q55
185	I37_Q54
186	I37_Q53
187	I37_Q52
188	I37_Q51
189	I37_Q50
190	I37_Q49
191	I36_Q72
192	I36_Q71
193	I36_Q70
194	I36_Q69

195	I36_Q68
196	I36_Q67
197	I36_Q66
198	I36_Q65
199	I36_Q64
200	I36_Q63
201	I36_Q62
202	I36_Q61
203	I36_Q60
204	I36_Q59
205	I36_Q58
206	I36_Q57
207	I36_Q56
208	I36_Q55
209	I36_Q54
210	I36_Q53
211	I36_Q52
212	I36_Q51
213	I36_Q50

214	I36_Q49
215	I35_Q72
216	I35_Q71
217	I35_Q70
218	I35_Q69
219	I35_Q68
220	I35_Q67
221	I35_Q66
222	I35_Q65
223	I35_Q64
224	I35_Q63
225	I35_Q62
226	I35_Q61
227	I35_Q60
228	I35_Q59
229	I35_Q58
230	I35_Q57
231	I35_Q56

Array Index	Correlation
Correlator_Counts_21	
1	I35_Q55
2	I35_Q54
3	I35_Q53
4	I35_Q52
5	I35_Q51
6	I35_Q50
7	I35_Q49
8	I34_Q72
9	I34_Q71
10	I34_Q70

11	I34_Q69
12	I34_Q68
13	I34_Q67
14	I34_Q66
15	I34_Q65
16	I34_Q64
17	I34_Q63
18	I34_Q62
19	I34_Q61
20	I34_Q60
21	I34_Q59
22	I34_Q58

23	I34_Q57
24	I34_Q56
25	I34_Q55
26	I34_Q54
27	I34_Q53
28	I34_Q52
29	I34_Q51
30	I34_Q50
31	I34_Q49
32	I33_Q72
33	I33_Q71
34	I33_Q70

35	I33_Q69
36	I33_Q68
37	I33_Q67
38	I33_Q66
39	I33_Q65
40	I33_Q64
41	I33_Q63
42	I33_Q62
43	I33_Q61
44	I33_Q60
45	I33_Q59
46	I33_Q58
47	I33_Q57
48	I33_Q56
49	I33_Q55
50	I33_Q54
51	I33_Q53
52	I33_Q52
53	I33_Q51
54	I33_Q50
55	I33_Q49
56	I32_Q72
57	I32_Q71
58	I32_Q70
59	I32_Q69
60	I32_Q68
61	I32_Q67
62	I32_Q66
63	I32_Q65
64	I32_Q64
65	I32_Q63
66	I32_Q62

67	I32_Q61
68	I32_Q60
69	I32_Q59
70	I32_Q58
71	I32_Q57
72	I32_Q56
73	I32_Q55
74	I32_Q54
75	I32_Q53
76	I32_Q52
77	I32_Q51
78	I32_Q50
79	I32_Q49
80	I31_Q72
81	I31_Q71
82	I31_Q70
83	I31_Q69
84	I31_Q68
85	I31_Q67
86	I31_Q66
87	I31_Q65
88	I31_Q64
89	I31_Q63
90	I31_Q62
91	I31_Q61
92	I31_Q60
93	I31_Q59
94	I31_Q58
95	I31_Q57
96	I31_Q56
97	I31_Q55
98	I31_Q54

99	I31_Q53
100	I31_Q52
101	I31_Q51
102	I31_Q50
103	I31_Q49
104	I30_Q72
105	I30_Q71
106	I30_Q70
107	I30_Q69
108	I30_Q68
109	I30_Q67
110	I30_Q66
111	I30_Q65
112	I30_Q64
113	I30_Q63
114	I30_Q62
115	I30_Q61
116	I30_Q60
117	I30_Q59
118	I30_Q58
119	I30_Q57
120	I30_Q56
121	I30_Q55
122	I30_Q54
123	I30_Q53
124	I30_Q52
125	I30_Q51
126	I30_Q50
127	I30_Q49
128	I29_Q72
129	I29_Q71
130	I29_Q70

131	I29_Q69
132	I29_Q68
133	I29_Q67
134	I29_Q66
135	I29_Q65
136	I29_Q64
137	I29_Q63
138	I29_Q62
139	I29_Q61
140	I29_Q60
141	I29_Q59
142	I29_Q58
143	I29_Q57
144	I29_Q56
145	I29_Q55
146	I29_Q54
147	I29_Q53
148	I29_Q52
149	I29_Q51
150	I29_Q50
151	I29_Q49
152	I28_Q72
153	I28_Q71
154	I28_Q70
155	I28_Q69
156	I28_Q68
157	I28_Q67
158	I28_Q66
159	I28_Q65
160	I28_Q64
161	I28_Q63
162	I28_Q62

163	I28_Q61
164	I28_Q60
165	I28_Q59
166	I28_Q58
167	I28_Q57
168	I28_Q56
169	I28_Q55
170	I28_Q54
171	I28_Q53
172	I28_Q52
173	I28_Q51
174	I28_Q50
175	I28_Q49
176	I27_Q72
177	I27_Q71
178	I27_Q70
179	I27_Q69
180	I27_Q68
181	I27_Q67
182	I27_Q66
183	I27_Q65
184	I27_Q64
185	I27_Q63
186	I27_Q62
187	I27_Q61
188	I27_Q60
189	I27_Q59
190	I27_Q58
191	I27_Q57
192	I27_Q56
193	I27_Q55
194	I27_Q54

195	I27_Q53
196	I27_Q52
197	I27_Q51
198	I27_Q50
199	I27_Q49
200	I26_Q72
201	I26_Q71
202	I26_Q70
203	I26_Q69
204	I26_Q68
205	I26_Q67
206	I26_Q66
207	I26_Q65
208	I26_Q64
209	I26_Q63
210	I26_Q62
211	I26_Q61
212	I26_Q60
213	I26_Q59
214	I26_Q58
215	I26_Q57
216	I26_Q56
217	I26_Q55
218	I26_Q54
219	I26_Q53
220	I26_Q52
221	I26_Q51
222	I26_Q50
223	I26_Q49
224	I25_Q72
225	I25_Q71
226	I25_Q70

227	I25_Q69
228	I25_Q68

229	I25_Q67
230	I25_Q66

231	I25_Q65
-----	---------

Array Index	Correlation
Correlator_Counts_22	
1	I25_Q64
2	I25_Q63
3	I25_Q62
4	I25_Q61
5	I25_Q60
6	I25_Q59
7	I25_Q58
8	I25_Q57
9	I25_Q56
10	I25_Q55
11	I25_Q54
12	I25_Q53
13	I25_Q52
14	I25_Q51
15	I25_Q50
16	I25_Q49
17	0_1-5
18	0_0-5

Array Index	Correlation
Correlator_Counts_23	
1	1_1-6
2	1_0-6
3	I72_1
4	I72_I24
5	I72_I23
6	I72_I22

7	I72_I21
8	I72_I20
9	I72_I19
10	I72_I18
11	I72_I17
12	I72_I16
13	I72_I15
14	I72_I14

15	I72_I13
16	I72_I12
17	I72_I11
18	I72_I10
19	I72_I9
20	I72_I8
21	I72_I7
22	I72_I6

23	I72_I5
24	I72_I4
25	I72_I3
26	I72_I2
27	I72_I1
28	I72_0
29	I71_1
30	I71_I24
31	I71_I23
32	I71_I22
33	I71_I21
34	I71_I20
35	I71_I19
36	I71_I18
37	I71_I17
38	I71_I16
39	I71_I15
40	I71_I14
41	I71_I13
42	I71_I12
43	I71_I11
44	I71_I10
45	I71_I9
46	I71_I8
47	I71_I7
48	I71_I6
49	I71_I5
50	I71_I4
51	I71_I3
52	I71_I2
53	I71_I1
54	I71_0

55	I70_1
56	I70_I24
57	I70_I23
58	I70_I22
59	I70_I21
60	I70_I20
61	I70_I19
62	I70_I18
63	I70_I17
64	I70_I16
65	I70_I15
66	I70_I14
67	I70_I13
68	I70_I12
69	I70_I11
70	I70_I10
71	I70_I9
72	I70_I8
73	I70_I7
74	I70_I6
75	I70_I5
76	I70_I4
77	I70_I3
78	I70_I2
79	I70_I1
80	I70_0
81	I69_1
82	I69_I24
83	I69_I23
84	I69_I22
85	I69_I21
86	I69_I20

87	I69_I19
88	I69_I18
89	I69_I17
90	I69_I16
91	I69_I15
92	I69_I14
93	I69_I13
94	I69_I12
95	I69_I11
96	I69_I10
97	I69_I9
98	I69_I8
99	I69_I7
100	I69_I6
101	I69_I5
102	I69_I4
103	I69_I3
104	I69_I2
105	I69_I1
106	I69_0
107	I68_1
108	I68_I24
109	I68_I23
110	I68_I22
111	I68_I21
112	I68_I20
113	I68_I19
114	I68_I18
115	I68_I17
116	I68_I16
117	I68_I15
118	I68_I14

119	I68_I13
120	I68_I12
121	I68_I11
122	I68_I10
123	I68_I9
124	I68_I8
125	I68_I7
126	I68_I6
127	I68_I5
128	I68_I4
129	I68_I3
130	I68_I2
131	I68_I1
132	I68_0
133	I67_1
134	I67_I24
135	I67_I23
136	I67_I22
137	I67_I21
138	I67_I20
139	I67_I19
140	I67_I18
141	I67_I17
142	I67_I16
143	I67_I15
144	I67_I14
145	I67_I13
146	I67_I12
147	I67_I11
148	I67_I10
149	I67_I9

150	I67_I8
151	I67_I7
152	I67_I6
153	I67_I5
154	I67_I4
155	I67_I3
156	I67_I2
157	I67_I1
158	I67_0
159	I66_1
160	I66_I24
161	I66_I23
162	I66_I22
163	I66_I21
164	I66_I20
165	I66_I19
166	I66_I18
167	I66_I17
168	I66_I16
169	I66_I15
170	I66_I14
171	I66_I13
172	I66_I12
173	I66_I11
174	I66_I10
175	I66_I9
176	I66_I8
177	I66_I7
178	I66_I6
179	I66_I5
180	I66_I4

181	I66_I3
182	I66_I2
183	I66_I1
184	I66_0
185	I65_1
186	I65_I24
187	I65_I23
188	I65_I22
189	I65_I21
190	I65_I20
191	I65_I19
192	I65_I18
193	I65_I17
194	I65_I16
195	I65_I15
196	I65_I14
197	I65_I13
198	I65_I12
199	I65_I11
200	I65_I10
201	I65_I9
202	I65_I8
203	I65_I7
204	I65_I6
205	I65_I5
206	I65_I4
207	I65_I3
208	I65_I2
209	I65_I1
210	I65_0

Array Index	Correlation
Correlator_Counts_24	
1	I64_1
2	I64_I24
3	I64_I23
4	I64_I22
5	I64_I21
6	I64_I20
7	I64_I19
8	I64_I18
9	I64_I17
10	I64_I16
11	I64_I15
12	I64_I14
13	I64_I13
14	I64_I12
15	I64_I11
16	I64_I10
17	I64_I9
18	I64_I8
19	I64_I7
20	I64_I6
21	I64_I5
22	I64_I4
23	I64_I3
24	I64_I2
25	I64_I1
26	I64_0
27	I63_1
28	I63_I24
29	I63_I23
30	I63_I22

31	I63_I21
32	I63_I20
33	I63_I19
34	I63_I18
35	I63_I17
36	I63_I16
37	I63_I15
38	I63_I14
39	I63_I13
40	I63_I12
41	I63_I11
42	I63_I10
43	I63_I9
44	I63_I8
45	I63_I7
46	I63_I6
47	I63_I5
48	I63_I4
49	I63_I3
50	I63_I2
51	I63_I1
52	I63_0
53	I62_1
54	I62_I24
55	I62_I23
56	I62_I22
57	I62_I21
58	I62_I20
59	I62_I19
60	I62_I18
61	I62_I17
62	I62_I16

63	I62_I15
64	I62_I14
65	I62_I13
66	I62_I12
67	I62_I11
68	I62_I10
69	I62_I9
70	I62_I8
71	I62_I7
72	I62_I6
73	I62_I5
74	I62_I4
75	I62_I3
76	I62_I2
77	I62_I1
78	I62_0
79	I61_1
80	I61_I24
81	I61_I23
82	I61_I22
83	I61_I21
84	I61_I20
85	I61_I19
86	I61_I18
87	I61_I17
88	I61_I16
89	I61_I15
90	I61_I14
91	I61_I13
92	I61_I12
93	I61_I11
94	I61_I10

95	I61_I9
96	I61_I8
97	I61_I7
98	I61_I6
99	I61_I5
100	I61_I4
101	I61_I3
102	I61_I2
103	I61_I1
104	I61_0
105	I60_1
106	I60_I24
107	I60_I23
108	I60_I22
109	I60_I21
110	I60_I20
111	I60_I19
112	I60_I18
113	I60_I17
114	I60_I16
115	I60_I15
116	I60_I14
117	I60_I13
118	I60_I12
119	I60_I11
120	I60_I10
121	I60_I9
122	I60_I8
123	I60_I7
124	I60_I6
125	I60_I5
126	I60_I4

127	I60_I3
128	I60_I2
129	I60_I1
130	I60_0
131	I59_1
132	I59_I24
133	I59_I23
134	I59_I22
135	I59_I21
136	I59_I20
137	I59_I19
138	I59_I18
139	I59_I17
140	I59_I16
141	I59_I15
142	I59_I14
143	I59_I13
144	I59_I12
145	I59_I11
146	I59_I10
147	I59_I9
148	I59_I8
149	I59_I7
150	I59_I6
151	I59_I5
152	I59_I4
153	I59_I3
154	I59_I2
155	I59_I1
156	I59_0
157	I58_1
158	I58_I24

159	I58_I23
160	I58_I22
161	I58_I21
162	I58_I20
163	I58_I19
164	I58_I18
165	I58_I17
166	I58_I16
167	I58_I15
168	I58_I14
169	I58_I13
170	I58_I12
171	I58_I11
172	I58_I10
173	I58_I9
174	I58_I8
175	I58_I7
176	I58_I6
177	I58_I5
178	I58_I4
179	I58_I3
180	I58_I2
181	I58_I1
182	I58_0
183	I57_1
184	I57_I24
185	I57_I23
186	I57_I22
187	I57_I21
188	I57_I20
189	I57_I19
190	I57_I18

191	I57_I17
192	I57_I16
193	I57_I15
194	I57_I14
195	I57_I13
196	I57_I12
197	I57_I11
198	I57_I10
199	I57_I9
200	I57_I8
201	I57_I7
202	I57_I6
203	I57_I5
204	I57_I4
205	I57_I3

206	I57_I2
207	I57_I1
208	I57_0
209	I56_1
210	I56_I24
211	I56_I23
212	I56_I22
213	I56_I21
214	I56_I20
215	I56_I19
216	I56_I18
217	I56_I17
218	I56_I16
219	I56_I15
220	I56_I14

221	I56_I13
222	I56_I12
223	I56_I11
224	I56_I10
225	I56_I9
226	I56_I8
227	I56_I7
228	I56_I6
229	I56_I5
230	I56_I4
231	I56_I3

Array Index	Correlation
Correlator_Counts_25	
1	I56_I2
2	I56_I1
3	I56_0
4	I55_1
5	I55_I24
6	I55_I23
7	I55_I22
8	I55_I21
9	I55_I20
10	I55_I19
11	I55_I18
12	I55_I17
13	I55_I16
14	I55_I15

15	I55_I14
16	I55_I13
17	I55_I12
18	I55_I11
19	I55_I10
20	I55_I9
21	I55_I8
22	I55_I7
23	I55_I6
24	I55_I5
25	I55_I4
26	I55_I3
27	I55_I2
28	I55_I1
29	I55_0
30	I54_1

31	I54_I24
32	I54_I23
33	I54_I22
34	I54_I21
35	I54_I20
36	I54_I19
37	I54_I18
38	I54_I17
39	I54_I16
40	I54_I15
41	I54_I14
42	I54_I13
43	I54_I12
44	I54_I11
45	I54_I10
46	I54_I9

47	I54_I8
48	I54_I7
49	I54_I6
50	I54_I5
51	I54_I4
52	I54_I3
53	I54_I2
54	I54_I1
55	I54_0
56	I53_1
57	I53_I24
58	I53_I23
59	I53_I22
60	I53_I21
61	I53_I20
62	I53_I19
63	I53_I18
64	I53_I17
65	I53_I16
66	I53_I15
67	I53_I14
68	I53_I13
69	I53_I12
70	I53_I11
71	I53_I10
72	I53_I9
73	I53_I8
74	I53_I7
75	I53_I6
76	I53_I5
77	I53_I4
78	I53_I3

79	I53_I2
80	I53_I1
81	I53_0
82	I52_1
83	I52_I24
84	I52_I23
85	I52_I22
86	I52_I21
87	I52_I20
88	I52_I19
89	I52_I18
90	I52_I17
91	I52_I16
92	I52_I15
93	I52_I14
94	I52_I13
95	I52_I12
96	I52_I11
97	I52_I10
98	I52_I9
99	I52_I8
100	I52_I7
101	I52_I6
102	I52_I5
103	I52_I4
104	I52_I3
105	I52_I2
106	I52_I1
107	I52_0
108	I51_1
109	I51_I24
110	I51_I23

111	I51_I22
112	I51_I21
113	I51_I20
114	I51_I19
115	I51_I18
116	I51_I17
117	I51_I16
118	I51_I15
119	I51_I14
120	I51_I13
121	I51_I12
122	I51_I11
123	I51_I10
124	I51_I9
125	I51_I8
126	I51_I7
127	I51_I6
128	I51_I5
129	I51_I4
130	I51_I3
131	I51_I2
132	I51_I1
133	I51_0
134	I50_1
135	I50_I24
136	I50_I23
137	I50_I22
138	I50_I21
139	I50_I20
140	I50_I19
141	I50_I18
142	I50_I17

143	I50_I16
144	I50_I15
145	I50_I14
146	I50_I13
147	I50_I12
148	I50_I11
149	I50_I10
150	I50_I9
151	I50_I8
152	I50_I7
153	I50_I6
154	I50_I5
155	I50_I4
156	I50_I3
157	I50_I2

158	I50_I1
159	I50_0
160	I49_1
161	I49_I24
162	I49_I23
163	I49_I22
164	I49_I21
165	I49_I20
166	I49_I19
167	I49_I18
168	I49_I17
169	I49_I16
170	I49_I15
171	I49_I14
172	I49_I13

173	I49_I12
174	I49_I11
175	I49_I10
176	I49_I9
177	I49_I8
178	I49_I7
179	I49_I6
180	I49_I5
181	I49_I4
182	I49_I3
183	I49_I2
184	I49_I1
185	I49_0
186	0_1-6
187	0_0-6

Array Index	Correlation
Correlator_Counts_26	
1	1_1-7
2	1_0-7
3	I72_I48
4	I72_I47
5	I72_I46
6	I72_I45
7	I72_I44
8	I72_I43
9	I72_I42
10	I72_I41
11	I72_I40
12	I72_I39
13	I72_I38

14	I72_I37
15	I72_I36
16	I72_I35
17	I72_I34
18	I72_I33
19	I72_I32
20	I72_I31
21	I72_I30
22	I72_I29
23	I72_I28
24	I72_I27
25	I72_I26
26	I72_I25
27	I71_I48
28	I71_I47

29	I71_I46
30	I71_I45
31	I71_I44
32	I71_I43
33	I71_I42
34	I71_I41
35	I71_I40
36	I71_I39
37	I71_I38
38	I71_I37
39	I71_I36
40	I71_I35
41	I71_I34

Array Index	Correlation
Correlator_Counts_27	
1	I71_I33
2	I71_I32
3	I71_I31
4	I71_I30
5	I71_I29
6	I71_I28
7	I71_I27
8	I71_I26
9	I71_I25
10	I70_I48
11	I70_I47
12	I70_I46
13	I70_I45
14	I70_I44
15	I70_I43
16	I70_I42
17	I70_I41
18	I70_I40
19	I70_I39
20	I70_I38
21	I70_I37
22	I70_I36
23	I70_I35
24	I70_I34
25	I70_I33
26	I70_I32
27	I70_I31
28	I70_I30
29	I70_I29
30	I70_I28

31	I70_I27
32	I70_I26
33	I70_I25
34	I69_I48
35	I69_I47
36	I69_I46
37	I69_I45
38	I69_I44
39	I69_I43
40	I69_I42
41	I69_I41
42	I69_I40
43	I69_I39
44	I69_I38
45	I69_I37
46	I69_I36
47	I69_I35
48	I69_I34
49	I69_I33
50	I69_I32
51	I69_I31
52	I69_I30
53	I69_I29
54	I69_I28
55	I69_I27
56	I69_I26
57	I69_I25
58	I68_I48
59	I68_I47
60	I68_I46
61	I68_I45
62	I68_I44

63	I68_I43
64	I68_I42
65	I68_I41
66	I68_I40
67	I68_I39
68	I68_I38
69	I68_I37
70	I68_I36
71	I68_I35
72	I68_I34
73	I68_I33
74	I68_I32
75	I68_I31
76	I68_I30
77	I68_I29
78	I68_I28
79	I68_I27
80	I68_I26
81	I68_I25
82	I67_I48
83	I67_I47
84	I67_I46
85	I67_I45
86	I67_I44
87	I67_I43
88	I67_I42
89	I67_I41
90	I67_I40
91	I67_I39
92	I67_I38
93	I67_I37
94	I67_I36

95	I67_I35
96	I67_I34
97	I67_I33
98	I67_I32
99	I67_I31
100	I67_I30
101	I67_I29
102	I67_I28
103	I67_I27
104	I67_I26
105	I67_I25
106	I66_I48
107	I66_I47
108	I66_I46
109	I66_I45
110	I66_I44
111	I66_I43
112	I66_I42
113	I66_I41
114	I66_I40
115	I66_I39
116	I66_I38
117	I66_I37
118	I66_I36
119	I66_I35
120	I66_I34
121	I66_I33
122	I66_I32
123	I66_I31
124	I66_I30
125	I66_I29
126	I66_I28

127	I66_I27
128	I66_I26
129	I66_I25
130	I65_I48
131	I65_I47
132	I65_I46
133	I65_I45
134	I65_I44
135	I65_I43
136	I65_I42
137	I65_I41
138	I65_I40
139	I65_I39
140	I65_I38
141	I65_I37
142	I65_I36
143	I65_I35
144	I65_I34
145	I65_I33
146	I65_I32
147	I65_I31
148	I65_I30
149	I65_I29
150	I65_I28
151	I65_I27
152	I65_I26
153	I65_I25
154	I64_I48
155	I64_I47
156	I64_I46
157	I64_I45
158	I64_I44

159	I64_I43
160	I64_I42
161	I64_I41
162	I64_I40
163	I64_I39
164	I64_I38
165	I64_I37
166	I64_I36
167	I64_I35
168	I64_I34
169	I64_I33
170	I64_I32
171	I64_I31
172	I64_I30
173	I64_I29
174	I64_I28
175	I64_I27
176	I64_I26
177	I64_I25
178	I63_I48
179	I63_I47
180	I63_I46
181	I63_I45
182	I63_I44
183	I63_I43
184	I63_I42
185	I63_I41
186	I63_I40
187	I63_I39
188	I63_I38
189	I63_I37
190	I63_I36

191	I63_I35
192	I63_I34
193	I63_I33
194	I63_I32
195	I63_I31
196	I63_I30
197	I63_I29
198	I63_I28
199	I63_I27
200	I63_I26
201	I63_I25
202	I62_I48
203	I62_I47
204	I62_I46
205	I62_I45

206	I62_I44
207	I62_I43
208	I62_I42
209	I62_I41
210	I62_I40
211	I62_I39
212	I62_I38
213	I62_I37
214	I62_I36
215	I62_I35
216	I62_I34
217	I62_I33
218	I62_I32
219	I62_I31
220	I62_I30

221	I62_I29
222	I62_I28
223	I62_I27
224	I62_I26
225	I62_I25
226	I61_I48
227	I61_I47
228	I61_I46
229	I61_I45
230	I61_I44
231	I61_I43

Array Index	Correlation
Correlator_Counts_28	
1	I61_I42
2	I61_I41
3	I61_I40
4	I61_I39
5	I61_I38
6	I61_I37
7	I61_I36
8	I61_I35
9	I61_I34
10	I61_I33
11	I61_I32
12	I61_I31
13	I61_I30
14	I61_I29

15	I61_I28
16	I61_I27
17	I61_I26
18	I61_I25
19	I60_I48
20	I60_I47
21	I60_I46
22	I60_I45
23	I60_I44
24	I60_I43
25	I60_I42
26	I60_I41
27	I60_I40
28	I60_I39
29	I60_I38
30	I60_I37

31	I60_I36
32	I60_I35
33	I60_I34
34	I60_I33
35	I60_I32
36	I60_I31
37	I60_I30
38	I60_I29
39	I60_I28
40	I60_I27
41	I60_I26
42	I60_I25
43	I59_I48
44	I59_I47
45	I59_I46
46	I59_I45

47	I59_I44
48	I59_I43
49	I59_I42
50	I59_I41
51	I59_I40
52	I59_I39
53	I59_I38
54	I59_I37
55	I59_I36
56	I59_I35
57	I59_I34
58	I59_I33
59	I59_I32
60	I59_I31
61	I59_I30
62	I59_I29
63	I59_I28
64	I59_I27
65	I59_I26
66	I59_I25
67	I58_I48
68	I58_I47
69	I58_I46
70	I58_I45
71	I58_I44
72	I58_I43
73	I58_I42
74	I58_I41
75	I58_I40
76	I58_I39
77	I58_I38
78	I58_I37

79	I58_I36
80	I58_I35
81	I58_I34
82	I58_I33
83	I58_I32
84	I58_I31
85	I58_I30
86	I58_I29
87	I58_I28
88	I58_I27
89	I58_I26
90	I58_I25
91	I57_I48
92	I57_I47
93	I57_I46
94	I57_I45
95	I57_I44
96	I57_I43
97	I57_I42
98	I57_I41
99	I57_I40
100	I57_I39
101	I57_I38
102	I57_I37
103	I57_I36
104	I57_I35
105	I57_I34
106	I57_I33
107	I57_I32
108	I57_I31
109	I57_I30
110	I57_I29

111	I57_I28
112	I57_I27
113	I57_I26
114	I57_I25
115	I56_I48
116	I56_I47
117	I56_I46
118	I56_I45
119	I56_I44
120	I56_I43
121	I56_I42
122	I56_I41
123	I56_I40
124	I56_I39
125	I56_I38
126	I56_I37
127	I56_I36
128	I56_I35
129	I56_I34
130	I56_I33
131	I56_I32
132	I56_I31
133	I56_I30
134	I56_I29
135	I56_I28
136	I56_I27
137	I56_I26
138	I56_I25
139	I55_I48
140	I55_I47
141	I55_I46
142	I55_I45

143	I55_I44
144	I55_I43
145	I55_I42
146	I55_I41
147	I55_I40
148	I55_I39
149	I55_I38
150	I55_I37
151	I55_I36
152	I55_I35
153	I55_I34
154	I55_I33
155	I55_I32
156	I55_I31
157	I55_I30
158	I55_I29
159	I55_I28
160	I55_I27
161	I55_I26
162	I55_I25
163	I54_I48
164	I54_I47
165	I54_I46
166	I54_I45
167	I54_I44
168	I54_I43
169	I54_I42
170	I54_I41
171	I54_I40
172	I54_I39

173	I54_I38
174	I54_I37
175	I54_I36
176	I54_I35
177	I54_I34
178	I54_I33
179	I54_I32
180	I54_I31
181	I54_I30
182	I54_I29
183	I54_I28
184	I54_I27
185	I54_I26
186	I54_I25
187	I53_I48
188	I53_I47
189	I53_I46
190	I53_I45
191	I53_I44
192	I53_I43
193	I53_I42
194	I53_I41
195	I53_I40
196	I53_I39
197	I53_I38
198	I53_I37
199	I53_I36
200	I53_I35
201	I53_I34
202	I53_I33

203	I53_I32
204	I53_I31
205	I53_I30
206	I53_I29
207	I53_I28
208	I53_I27
209	I53_I26
210	I53_I25
211	I52_I48
212	I52_I47
213	I52_I46
214	I52_I45
215	I52_I44
216	I52_I43
217	I52_I42
218	I52_I41
219	I52_I40
220	I52_I39
221	I52_I38
222	I52_I37
223	I52_I36
224	I52_I35
225	I52_I34
226	I52_I33
227	I52_I32
228	I52_I31
229	I52_I30
230	I52_I29
231	I52_I28

Array Index	Correlation
Correlator_Counts_29	
1	I52_I27
2	I52_I26
3	I52_I25
4	I51_I48
5	I51_I47
6	I51_I46
7	I51_I45
8	I51_I44
9	I51_I43
10	I51_I42
11	I51_I41
12	I51_I40
13	I51_I39
14	I51_I38
15	I51_I37
16	I51_I36
17	I51_I35
18	I51_I34
19	I51_I33
20	I51_I32
21	I51_I31
22	I51_I30
23	I51_I29
24	I51_I28
25	I51_I27

26	I51_I26
27	I51_I25
28	I50_I48
29	I50_I47
30	I50_I46
31	I50_I45
32	I50_I44
33	I50_I43
34	I50_I42
35	I50_I41
36	I50_I40
37	I50_I39
38	I50_I38
39	I50_I37
40	I50_I36
41	I50_I35
42	I50_I34
43	I50_I33
44	I50_I32
45	I50_I31
46	I50_I30
47	I50_I29
48	I50_I28
49	I50_I27
50	I50_I26
51	I50_I25
52	I49_I48

53	I49_I47
54	I49_I46
55	I49_I45
56	I49_I44
57	I49_I43
58	I49_I42
59	I49_I41
60	I49_I40
61	I49_I39
62	I49_I38
63	I49_I37
64	I49_I36
65	I49_I35
66	I49_I34
67	I49_I33
68	I49_I32
69	I49_I31
70	I49_I30
71	I49_I29
72	I49_I28
73	I49_I27
74	I49_I26
75	I49_I25
76	0_1-7
77	0_0-7

Array Index	Correlation
Correlator_Counts_30	
1	1_1-8
2	1_0-8

3	I72_Q72
4	I72_I71
5	I72_I70
6	I72_I69

7	I72_I68
8	I72_I67
9	I72_I66
10	I72_I65

11	I72_I64
12	I72_I63
13	I72_I62
14	I72_I61
15	I72_I60
16	I72_I59
17	I72_I58
18	I72_I57
19	I72_I56
20	I72_I55
21	I72_I54
22	I72_I53
23	I72_I52
24	I72_I51
25	I72_I50
26	I72_I49
27	I71_Q72
28	I71_Q71
29	I71_I70
30	I71_I69
31	I71_I68
32	I71_I67
33	I71_I66
34	I71_I65
35	I71_I64
36	I71_I63
37	I71_I62
38	I71_I61
39	I71_I60
40	I71_I59
41	I71_I58
42	I71_I57

43	I71_I56
44	I71_I55
45	I71_I54
46	I71_I53
47	I71_I52
48	I71_I51
49	I71_I50
50	I71_I49
51	I70_Q72
52	I70_Q71
53	I70_Q70
54	I70_I69
55	I70_I68
56	I70_I67
57	I70_I66
58	I70_I65
59	I70_I64
60	I70_I63
61	I70_I62
62	I70_I61
63	I70_I60
64	I70_I59
65	I70_I58
66	I70_I57
67	I70_I56
68	I70_I55
69	I70_I54
70	I70_I53
71	I70_I52
72	I70_I51
73	I70_I50
74	I70_I49

75	I69_Q72
76	I69_Q71
77	I69_Q70
78	I69_Q69
79	I69_I68
80	I69_I67
81	I69_I66
82	I69_I65
83	I69_I64
84	I69_I63
85	I69_I62
86	I69_I61
87	I69_I60
88	I69_I59
89	I69_I58
90	I69_I57
91	I69_I56
92	I69_I55
93	I69_I54
94	I69_I53
95	I69_I52
96	I69_I51
97	I69_I50
98	I69_I49
99	I68_Q72
100	I68_Q71
101	I68_Q70
102	I68_Q69
103	I68_Q68
104	I68_I67
105	I68_I66
106	I68_I65

107	I68_I64
108	I68_I63
109	I68_I62
110	I68_I61
111	I68_I60
112	I68_I59
113	I68_I58
114	I68_I57
115	I68_I56
116	I68_I55
117	I68_I54
118	I68_I53
119	I68_I52
120	I68_I51
121	I68_I50

122	I68_I49
123	I67_Q72
124	I67_Q71
125	I67_Q70
126	I67_Q69
127	I67_Q68
128	I67_Q67
129	I67_I66
130	I67_I65
131	I67_I64
132	I67_I63
133	I67_I62
134	I67_I61
135	I67_I60
136	I67_I59

137	I67_I58
138	I67_I57
139	I67_I56
140	I67_I55
141	I67_I54
142	I67_I53
143	I67_I52
144	I67_I51
145	I67_I50
146	I67_I49
147	I66_Q72
148	I66_Q71
149	I66_Q70
150	I66_Q69
151	I66_Q68

Array Index	Correlation
Correlator_Counts_31	
1	I66_Q67
2	I66_Q66
3	I66_I65
4	I66_I64
5	I66_I63
6	I66_I62
7	I66_I61
8	I66_I60
9	I66_I59
10	I66_I58
11	I66_I57
12	I66_I56
13	I66_I55
14	I66_I54

15	I66_I53
16	I66_I52
17	I66_I51
18	I66_I50
19	I66_I49
20	I65_Q72
21	I65_Q71
22	I65_Q70
23	I65_Q69
24	I65_Q68
25	I65_Q67
26	I65_Q66
27	I65_Q65
28	I65_I64
29	I65_I63
30	I65_I62

31	I65_I61
32	I65_I60
33	I65_I59
34	I65_I58
35	I65_I57
36	I65_I56
37	I65_I55
38	I65_I54
39	I65_I53
40	I65_I52
41	I65_I51
42	I65_I50
43	I65_I49
44	I64_Q72
45	I64_Q71
46	I64_Q70

47	I64_Q69
48	I64_Q68
49	I64_Q67
50	I64_Q66
51	I64_Q65
52	I64_Q64
53	I64_I63
54	I64_I62
55	I64_I61
56	I64_I60
57	I64_I59
58	I64_I58
59	I64_I57
60	I64_I56
61	I64_I55
62	I64_I54
63	I64_I53
64	I64_I52
65	I64_I51
66	I64_I50
67	I64_I49
68	I63_Q72
69	I63_Q71
70	I63_Q70
71	I63_Q69
72	I63_Q68
73	I63_Q67
74	I63_Q66
75	I63_Q65
76	I63_Q64
77	I63_Q63
78	I63_I62

79	I63_I61
80	I63_I60
81	I63_I59
82	I63_I58
83	I63_I57
84	I63_I56
85	I63_I55
86	I63_I54
87	I63_I53
88	I63_I52
89	I63_I51
90	I63_I50
91	I63_I49
92	I62_Q72
93	I62_Q71
94	I62_Q70
95	I62_Q69
96	I62_Q68
97	I62_Q67
98	I62_Q66
99	I62_Q65
100	I62_Q64
101	I62_Q63
102	I62_Q62
103	I62_I61
104	I62_I60
105	I62_I59
106	I62_I58
107	I62_I57
108	I62_I56
109	I62_I55
110	I62_I54

111	I62_I53
112	I62_I52
113	I62_I51
114	I62_I50
115	I62_I49
116	I61_Q72
117	I61_Q71
118	I61_Q70
119	I61_Q69
120	I61_Q68
121	I61_Q67
122	I61_Q66
123	I61_Q65
124	I61_Q64
125	I61_Q63
126	I61_Q62
127	I61_Q61
128	I61_I60
129	I61_I59
130	I61_I58
131	I61_I57
132	I61_I56
133	I61_I55
134	I61_I54
135	I61_I53
136	I61_I52
137	I61_I51
138	I61_I50
139	I61_I49
140	I60_Q72
141	I60_Q71
142	I60_Q70

143	I60_Q69
144	I60_Q68
145	I60_Q67
146	I60_Q66
147	I60_Q65
148	I60_Q64
149	I60_Q63
150	I60_Q62
151	I60_Q61
152	I60_Q60
153	I60_I59
154	I60_I58
155	I60_I57
156	I60_I56
157	I60_I55
158	I60_I54
159	I60_I53
160	I60_I52
161	I60_I51
162	I60_I50
163	I60_I49
164	I59_Q72
165	I59_Q71
166	I59_Q70
167	I59_Q69
168	I59_Q68
169	I59_Q67
170	I59_Q66
171	I59_Q65
172	I59_Q64

173	I59_Q63
174	I59_Q62
175	I59_Q61
176	I59_Q60
177	I59_Q59
178	I59_I58
179	I59_I57
180	I59_I56
181	I59_I55
182	I59_I54
183	I59_I53
184	I59_I52
185	I59_I51
186	I59_I50
187	I59_I49
188	I58_Q72
189	I58_Q71
190	I58_Q70
191	I58_Q69
192	I58_Q68
193	I58_Q67
194	I58_Q66
195	I58_Q65
196	I58_Q64
197	I58_Q63
198	I58_Q62
199	I58_Q61
200	I58_Q60
201	I58_Q59
202	I58_Q58

203	I58_I57
204	I58_I56
205	I58_I55
206	I58_I54
207	I58_I53
208	I58_I52
209	I58_I51
210	I58_I50
211	I58_I49
212	I57_Q72
213	I57_Q71
214	I57_Q70
215	I57_Q69
216	I57_Q68
217	I57_Q67
218	I57_Q66
219	I57_Q65
220	I57_Q64
221	I57_Q63
222	I57_Q62
223	I57_Q61
224	I57_Q60
225	I57_Q59
226	I57_Q58
227	I57_Q57
228	I57_I56
229	I57_I55
230	I57_I54
231	I57_I53

Array Index	Correlation
Correlator_Counts_32	
1	I57_I52
2	I57_I51
3	I57_I50
4	I57_I49
5	I56_Q72
6	I56_Q71
7	I56_Q70
8	I56_Q69
9	I56_Q68
10	I56_Q67
11	I56_Q66
12	I56_Q65
13	I56_Q64
14	I56_Q63
15	I56_Q62
16	I56_Q61
17	I56_Q60
18	I56_Q59
19	I56_Q58
20	I56_Q57
21	I56_Q56
22	I56_I55
23	I56_I54
24	I56_I53
25	I56_I52
26	I56_I51
27	I56_I50
28	I56_I49
29	I55_Q72
30	I55_Q71

31	I55_Q70
32	I55_Q69
33	I55_Q68
34	I55_Q67
35	I55_Q66
36	I55_Q65
37	I55_Q64
38	I55_Q63
39	I55_Q62
40	I55_Q61
41	I55_Q60
42	I55_Q59
43	I55_Q58
44	I55_Q57
45	I55_Q56
46	I55_Q55
47	I55_I54
48	I55_I53
49	I55_I52
50	I55_I51
51	I55_I50
52	I55_I49
53	I54_Q72
54	I54_Q71
55	I54_Q70
56	I54_Q69
57	I54_Q68
58	I54_Q67
59	I54_Q66
60	I54_Q65
61	I54_Q64
62	I54_Q63

63	I54_Q62
64	I54_Q61
65	I54_Q60
66	I54_Q59
67	I54_Q58
68	I54_Q57
69	I54_Q56
70	I54_Q55
71	I54_Q54
72	I54_I53
73	I54_I52
74	I54_I51
75	I54_I50
76	I54_I49
77	I53_Q72
78	I53_Q71
79	I53_Q70
80	I53_Q69
81	I53_Q68
82	I53_Q67
83	I53_Q66
84	I53_Q65
85	I53_Q64
86	I53_Q63
87	I53_Q62
88	I53_Q61
89	I53_Q60
90	I53_Q59
91	I53_Q58
92	I53_Q57
93	I53_Q56
94	I53_Q55

95	I53_Q54
96	I53_Q53
97	I53_I52
98	I53_I51
99	I53_I50
100	I53_I49
101	I52_Q72
102	I52_Q71
103	I52_Q70
104	I52_Q69
105	I52_Q68
106	I52_Q67
107	I52_Q66
108	I52_Q65
109	I52_Q64
110	I52_Q63
111	I52_Q62
112	I52_Q61
113	I52_Q60
114	I52_Q59
115	I52_Q58
116	I52_Q57
117	I52_Q56
118	I52_Q55
119	I52_Q54
120	I52_Q53
121	I52_Q52
122	I52_I51
123	I52_I50
124	I52_I49
125	I51_Q72
126	I51_Q71

127	I51_Q70
128	I51_Q69
129	I51_Q68
130	I51_Q67
131	I51_Q66
132	I51_Q65
133	I51_Q64
134	I51_Q63
135	I51_Q62
136	I51_Q61
137	I51_Q60
138	I51_Q59
139	I51_Q58
140	I51_Q57
141	I51_Q56
142	I51_Q55
143	I51_Q54
144	I51_Q53
145	I51_Q52
146	I51_Q51
147	I51_I50
148	I51_I49
149	I50_Q72
150	I50_Q71
151	I50_Q70
152	I50_Q69
153	I50_Q68
154	I50_Q67
155	I50_Q66
156	I50_Q65
157	I50_Q64
158	I50_Q63

159	I50_Q62
160	I50_Q61
161	I50_Q60
162	I50_Q59
163	I50_Q58
164	I50_Q57
165	I50_Q56
166	I50_Q55
167	I50_Q54
168	I50_Q53
169	I50_Q52
170	I50_Q51
171	I50_Q50
172	I50_I49
173	I49_Q72
174	I49_Q71
175	I49_Q70
176	I49_Q69
177	I49_Q68
178	I49_Q67
179	I49_Q66
180	I49_Q65
181	I49_Q64
182	I49_Q63
183	I49_Q62
184	I49_Q61
185	I49_Q60
186	I49_Q59
187	I49_Q58
188	I49_Q57
189	I49_Q56
190	I49_Q55

191	I49_Q54
192	I49_Q53
193	I49_Q52

194	I49_Q51
195	I49_Q50
196	I49_Q49

197	0_1-8
198	0_0-8

End of Document